



Informatica®

10.1.1 HotFix 2

Security Guide

© Copyright Informatica LLC 2013, 2019

This software and documentation are provided only under a separate license agreement containing restrictions on use and disclosure. No part of this document may be reproduced or transmitted in any form, by any means (electronic, photocopying, recording or otherwise) without prior consent of Informatica LLC.

Informatica, the Informatica logo, Informatica Cloud, PowerCenter, and PowerExchange are trademarks or registered trademarks of Informatica LLC in the United States and many jurisdictions throughout the world. A current list of Informatica trademarks is available on the web at <https://www.informatica.com/trademarks.html>. Other company and product names may be trade names or trademarks of their respective owners.

Portions of this software and/or documentation are subject to copyright held by third parties, including without limitation: Copyright DataDirect Technologies. All rights reserved. Copyright © Sun Microsystems. All rights reserved. Copyright © RSA Security Inc. All Rights Reserved. Copyright © Ordinal Technology Corp. All rights reserved. Copyright © Aandacht c.v. All rights reserved. Copyright Genivia, Inc. All rights reserved. Copyright Isomorphic Software. All rights reserved. Copyright © Meta Integration Technology, Inc. All rights reserved. Copyright © Intalio. All rights reserved. Copyright © Oracle. All rights reserved. Copyright © Adobe Systems Incorporated. All rights reserved. Copyright © DataArt, Inc. All rights reserved. Copyright © ComponentSource. All rights reserved. Copyright © Microsoft Corporation. All rights reserved. Copyright © Rogue Wave Software, Inc. All rights reserved. Copyright © Teradata Corporation. All rights reserved. Copyright © Yahoo! Inc. All rights reserved. Copyright © Glyph & Cog, LLC. All rights reserved. Copyright © Thinkmap, Inc. All rights reserved. Copyright © Clearpace Software Limited. All rights reserved. Copyright © Information Builders, Inc. All rights reserved. Copyright © OSS Nokalva, Inc. All rights reserved. Copyright Edifecs, Inc. All rights reserved. Copyright Cleo Communications, Inc. All rights reserved. Copyright © International Organization for Standardization 1986. All rights reserved. Copyright © ej-technologies GmbH. All rights reserved. Copyright © Jaspersoft Corporation. All rights reserved. Copyright © International Business Machines Corporation. All rights reserved. Copyright © yWorks GmbH. All rights reserved. Copyright © Lucent Technologies. All rights reserved. Copyright © University of Toronto. All rights reserved. Copyright © Daniel Veillard. All rights reserved. Copyright © Unicode, Inc. Copyright IBM Corp. All rights reserved. Copyright © MicroQuill Software Publishing, Inc. All rights reserved. Copyright © PassMark Software Pty Ltd. All rights reserved. Copyright © LogiXML, Inc. All rights reserved. Copyright © 2003-2010 Lorenzi Davide, All rights reserved. Copyright © Red Hat, Inc. All rights reserved. Copyright © The Board of Trustees of the Leland Stanford Junior University. All rights reserved. Copyright © EMC Corporation. All rights reserved. Copyright © Flexera Software. All rights reserved. Copyright © Jinfonet Software. All rights reserved. Copyright © Apple Inc. All rights reserved. Copyright © Telerik Inc. All rights reserved. Copyright © BEA Systems. All rights reserved. Copyright © PDFlib GmbH. All rights reserved. Copyright © Orientation in Objects GmbH. All rights reserved. Copyright © Tanuki Software, Ltd. All rights reserved. Copyright © Ricebridge. All rights reserved. Copyright © Sencha, Inc. All rights reserved. Copyright © Scalable Systems, Inc. All rights reserved. Copyright © jqWidgets. All rights reserved. Copyright © Tableau Software, Inc. All rights reserved. Copyright © MaxMind, Inc. All Rights Reserved. Copyright © TMate Software s.r.o. All rights reserved. Copyright © MapR Technologies Inc. All rights reserved. Copyright © Amazon Corporate LLC. All rights reserved. Copyright © Highsoft. All rights reserved. Copyright © Python Software Foundation. All rights reserved. Copyright © BeOpen.com. All rights reserved. Copyright © CNRI. All rights reserved.

This product includes software developed by the Apache Software Foundation (<http://www.apache.org/>), and/or other software which is licensed under various versions of the Apache License (the "License"). You may obtain a copy of these Licenses at <http://www.apache.org/licenses/>. Unless required by applicable law or agreed to in writing, software distributed under these Licenses is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the Licenses for the specific language governing permissions and limitations under the Licenses.

This product includes software which was developed by Mozilla (<http://www.mozilla.org/>), software copyright The JBoss Group, LLC, all rights reserved; software copyright © 1999-2006 by Bruno Lowagie and Paulo Soares and other software which is licensed under various versions of the GNU Lesser General Public License Agreement, which may be found at <http://www.gnu.org/licenses/lgpl.html>. The materials are provided free of charge by Informatica, "as-is", without warranty of any kind, either express or implied, including but not limited to the implied warranties of merchantability and fitness for a particular purpose.

The product includes ACE(TM) and TAO(TM) software copyrighted by Douglas C. Schmidt and his research group at Washington University, University of California, Irvine, and Vanderbilt University, Copyright (©) 1993-2006, all rights reserved.

This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit (copyright The OpenSSL Project. All Rights Reserved) and redistribution of this software is subject to terms available at <http://www.openssl.org> and <http://www.openssl.org/source/license.html>.

This product includes Curl software which is Copyright 1996-2013, Daniel Stenberg, <daniel@haxx.se>. All Rights Reserved. Permissions and limitations regarding this software are subject to terms available at <http://curl.haxx.se/docs/copyright.html>. Permission to use, copy, modify, and distribute this software for any purpose with or without fee is hereby granted, provided that the above copyright notice and this permission notice appear in all copies.

The product includes software copyright 2001-2005 (©) MetaStuff, Ltd. All Rights Reserved. Permissions and limitations regarding this software are subject to terms available at <http://www.dom4j.org/license.html>.

The product includes software copyright © 2004-2007, The Dojo Foundation. All Rights Reserved. Permissions and limitations regarding this software are subject to terms available at <http://dojotoolkit.org/license>.

This product includes ICU software which is copyright International Business Machines Corporation and others. All rights reserved. Permissions and limitations regarding this software are subject to terms available at <http://source.icu-project.org/repos/icu/icu/trunk/license.html>.

This product includes software copyright © 1996-2006 Per Bothner. All rights reserved. Your right to use such materials is set forth in the license which may be found at <http://www.gnu.org/software/kawa/Software-License.html>.

This product includes OSSP UUID software which is Copyright © 2002 Ralf S. Engelschall, Copyright © 2002 The OSSP Project Copyright © 2002 Cable & Wireless Deutschland. Permissions and limitations regarding this software are subject to terms available at <http://www.opensource.org/licenses/mit-license.php>.

This product includes software developed by Boost (<http://www.boost.org/>) or under the Boost software license. Permissions and limitations regarding this software are subject to terms available at http://www.boost.org/LICENSE_1_0.txt.

This product includes software copyright © 1997-2007 University of Cambridge. Permissions and limitations regarding this software are subject to terms available at <http://www.pcre.org/license.txt>.

This product includes software copyright © 2007 The Eclipse Foundation. All Rights Reserved. Permissions and limitations regarding this software are subject to terms available at <http://www.eclipse.org/org/documents/epl-v10.php> and at <http://www.eclipse.org/org/documents/edl-v10.php>.

This product includes software licensed under the terms at <http://www.tcl.tk/software/tcltk/license.html>, <http://www.bosrup.com/web/overlib/?License>, <http://www.stlport.org/doc/license.html>, <http://asm.ow2.org/license.html>, <http://www.cryptix.org/LICENSE.TXT>, <http://hsqldb.org/web/hsqLicense.html>, <http://httpunit.sourceforge.net/doc/license.html>, <http://jung.sourceforge.net/license.txt>, http://www.gzip.org/zlib/zlib_license.html, <http://www.openldap.org/software/release/license.html>, <http://www.libssh2.org>, <http://slf4j.org/license.html>, <http://www.sente.ch/software/OpenSourceLicense.html>, <http://fusesource.com/downloads/license-agreements/fuse-message-broker-v-5-3-license-agreement>, <http://antlr.org/license.html>, <http://aopalliance.sourceforge.net/>, <http://www.bouncycastle.org/license.html>, <http://www.jgraph.com/jgraphdownload.html>, <http://www.jcraft.com/jsch/LICENSE.txt>, http://jotm.objectweb.org/bsd_license.html, <http://www.w3.org/Consortium/Legal/2002/copyright-software-20021231>, <http://www.slf4j.org/license.html>, <http://nanoxml.sourceforge.net/orig/copyright.html>, <http://www.json.org/license.html>, <http://forge.ow2.org/projects/javaservice/>, <http://www.postgresql.org/about/license.html>, <http://www.sqlite.org/copyright.html>, <http://www.tcl.tk/software/tcltk/license.html>, <http://www.jaxen.org/faq.html>, <http://www.jdom.org/docs/faq.html>, <http://www.slf4j.org/license.html>, <http://www.iodbc.org/dataspace/iodbc/wiki/IODBC/License>, <http://www.keplerproject.org/md5/license.html>, <http://www.toedter.com/en/jcalendar/license.html>, <http://www.edankert.com/bounce/index.html>, <http://www.net-snmp.org/about/license.html>, <http://www.openmdx.org/#FAQ>, http://www.php.net/license/3_01.txt, <http://srp.stanford.edu/license.txt>;

<http://www.schneider.com/blowfish.html>; <http://www.jmock.org/license.html>; <http://xsom.java.net>; <http://benalman.com/about/license/>; <https://github.com/CreateJS/EaselJS/blob/master/src/easeljs/display/Bitmap.js>; <http://www.h2database.com/html/license.html#summary>; <http://jsoncpp.sourceforge.net/LICENSE>; <http://jdbc.postgresql.org/license.html>; <http://protobuf.googlecode.com/svn/trunk/src/google/protobuf/descriptor.proto>; <https://github.com/rantav/hector/blob/master/LICENSE>; <http://web.mit.edu/Kerberos/krb5-current/doc/mitK5license.html>; <http://jibx.sourceforge.net/jibx-license.html>; <https://github.com/lyokato/libgeohash/blob/master/LICENSE>; <https://github.com/hjiang/jsonxx/blob/master/LICENSE>; <https://code.google.com/p/lz4/>; <https://github.com/jedisct1/libsodium/blob/master/LICENSE>; <http://one-jar.sourceforge.net/index.php?page=documents&file=license>; <https://github.com/EsotericSoftware/kryo/blob/master/license.txt>; <http://www.scala-lang.org/license.html>; <https://github.com/tinkerpop/blueprints/blob/master/LICENSE.txt>; <http://gee.cs.oswego.edu/dl/classes/EDU/oswego/cs/dl/util/concurrent/intro.html>; <https://aws.amazon.com/asl/>; <https://github.com/twbs/bootstrap/blob/master/LICENSE>; <https://sourceforge.net/p/xmlunit/code/HEAD/tree/trunk/LICENSE.txt>; <https://github.com/documentcloud/underscore-contrib/blob/master/LICENSE>, and <https://github.com/apache/hbase/blob/master/LICENSE.txt>.

This product includes software licensed under the Academic Free License (<http://www.opensource.org/licenses/afl-3.0.php>), the Common Development and Distribution License (<http://www.opensource.org/licenses/cddl1.php>), the Common Public License (<http://www.opensource.org/licenses/cpl1.0.php>), the Sun Binary Code License Agreement Supplemental License Terms, the BSD License (<http://www.opensource.org/licenses/bsd-license.php>), the new BSD License (<http://opensource.org/licenses/BSD-3-Clause>), the MIT License (<http://www.opensource.org/licenses/mit-license.php>), the Artistic License (<http://www.opensource.org/licenses/artistic-license-1.0>) and the Initial Developer's Public License Version 1.0 (<http://www.firebirdsql.org/en/initial-developer-s-public-license-version-1-0/>).

This product includes software copyright © 2003-2006 Joe Walnes, 2006-2007 XStream Committers. All rights reserved. Permissions and limitations regarding this software are subject to terms available at <http://xstream.codehaus.org/license.html>. This product includes software developed by the Indiana University Extreme! Lab. For further information please visit <http://www.extreme.indiana.edu/>.

This product includes software Copyright (c) 2013 Frank Balluffi and Markus Moeller. All rights reserved. Permissions and limitations regarding this software are subject to terms of the MIT license.

See patents at <https://www.informatica.com/legal/patents.html>.

DISCLAIMER: Informatica LLC provides this documentation "as is" without warranty of any kind, either express or implied, including, but not limited to, the implied warranties of noninfringement, merchantability, or use for a particular purpose. Informatica LLC does not warrant that this software or documentation is error free. The information provided in this software or documentation may include technical inaccuracies or typographical errors. The information in this software and documentation is subject to change at any time without notice.

NOTICES

This Informatica product (the "Software") includes certain drivers (the "DataDirect Drivers") from DataDirect Technologies, an operating company of Progress Software Corporation ("DataDirect") which are subject to the following terms and conditions:

1. THE DATADIRECT DRIVERS ARE PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT.
2. IN NO EVENT WILL DATADIRECT OR ITS THIRD PARTY SUPPLIERS BE LIABLE TO THE END-USER CUSTOMER FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, CONSEQUENTIAL OR OTHER DAMAGES ARISING OUT OF THE USE OF THE ODBC DRIVERS, WHETHER OR NOT INFORMED OF THE POSSIBILITIES OF DAMAGES IN ADVANCE. THESE LIMITATIONS APPLY TO ALL CAUSES OF ACTION, INCLUDING, WITHOUT LIMITATION, BREACH OF CONTRACT, BREACH OF WARRANTY, NEGLIGENCE, STRICT LIABILITY, MISREPRESENTATION AND OTHER TORTS.

The information in this documentation is subject to change without notice. If you find any problems in this documentation, please report them to us in writing at Informatica LLC 2100 Seaport Blvd. Redwood City, CA 94063.

INFORMATICA LLC PROVIDES THE INFORMATION IN THIS DOCUMENT "AS IS" WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING WITHOUT ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND ANY WARRANTY OR CONDITION OF NON-INFRINGEMENT.

Publication Date: 2019-10-10

Table of Contents

Preface	11
Informatica Resources.	11
Informatica Network.	11
Informatica Knowledge Base.	11
Informatica Documentation.	11
Informatica Product Availability Matrixes.	12
Informatica Velocity.	12
Informatica Marketplace.	12
Informatica Global Customer Support.	12
 Chapter 1: Introduction to Informatica Security.....	13
Overview of Informatica Security.	13
Infrastructure Security.	14
Authentication.	14
Secure Domain Communication.	15
Secure Data Storage.	15
Operational Security.	16
Domain Configuration Repository.	16
Security Domain.	17
 Chapter 2: User Authentication.....	18
User Authentication Overview.	18
Native User Authentication.	19
LDAP User Authentication.	19
Kerberos Authentication.	20
SAML-based Single Sign-on for Informatica Web Applications.	20
 Chapter 3: LDAP Security Domains.....	21
LDAP Security Domains Overview.	21
Setting Up an LDAP Security Domain.	22
Step 1. Set Up the Connection to the LDAP Server.	22
Step 2. Configure a Security Domain.	23
Step 3. Schedule the Synchronization Times.	25
Using Nested Groups in the LDAP Directory Service.	26
Using a Self-Signed SSL Certificate.	26
Deleting an LDAP Security Domain.	27
 Chapter 4: Kerberos Authentication.....	28
Kerberos Overview.	28
How Kerberos Works in an Informatica Domain.	29

Preparing to Enable Kerberos Authentication.	31
Step 1. Determine the Kerberos Service Principal Level.	31
Step 2. Configure the Kerberos Configuration File.	31
Step 3. Create Kerberos Principal Accounts in Active Directory.	34
Step 4. Generate the Service Principal Name and Keytab File Name Formats.	35
Step 5. Generate the Keytab Files.	41
Step 6. Enable Delegation for the Kerberos Principal User Accounts in Active Directory.	44
Enabling Kerberos Authentication in a Domain.	45
Step 1. Enable Kerberos Authentication in the Domain.	46
Step 2. Update the Nodes in the Domain.	47
Enabling Kerberos on Informatica Nodes.	48
Step 1. Copy the Keytab Files to the Informatica Nodes.	49
Step 2. Enable Kerberos Authentication for Informatica Clients.	50
Enabling User Accounts to Use Kerberos Authentication.	50
Step 1. Import User Accounts from Active Directory into an LDAP Security Domain.	51
Step 2. Migrate Native User Privileges and Permissions to the Kerberos Security Domain.	55
Chapter 5: Domain Security.	57
Domain Security Overview.	57
Secure Communication Within the Domain.	58
Secure Communication for Services and the Service Manager.	58
Secure Domain Configuration Repository Database.	63
Secure PowerCenter Repository Database.	66
Secure Model Repository Database.	66
Secure Communication for Workflows and Sessions.	67
Secure Connections to a Web Application Service.	68
Requirements for Secure Connections to Web Application Services.	68
Enabling Secure Connections to the Administrator Tool.	69
Informatica Web Application Services.	69
Cipher Suites for the Informatica Domain.	71
Configure the Informatica Domain to Use Advanced Ciphers.	72
Create the Cipher Suite Lists.	72
Configure the Informatica Domain with a New Effective List of Cipher Suites.	72
Secure Sources and Targets.	73
Data Integration Service Sources and Targets.	74
PowerCenter Sources and Targets.	75
Secure Data Storage.	75
Secure Directory on UNIX.	75
Changing the Encryption Key from the Command Line.	76
Application Services and Ports.	79
Chapter 6: Single Sign-on for Informatica Web Applications.	82
SAML Authentication Overview.	82

SAML Authentication Process.	82
SAML-based Single Sign-on Setup.	83
Before You Enable Single Sign-on.	83
Step 1. Create a Security Domain for Web Application User Accounts.	84
Step 2. Export the Certificate from AD FS.	87
Step 3. Import the Certificate into the Informatica Truststore.	90
Step 4. Configure Active Directory Federation Services.	91
Step 5. Add Informatica Web Application URLs to AD FS.	98
Step 6. Enable SAML-based Single Sign-on.	100

Chapter 7: Security Management in Informatica Administrator..... 103

Using Informatica Administrator Overview.	103
User Security.	104
Encryption.	105
Authentication.	105
Authorization.	106
Security Tab.	107
Using the Search Section.	107
Using the Security Navigator.	107
Groups.	108
Users.	108
Roles.	109
Password Management.	109
Changing Your Password.	109
Domain Security Management.	110
User Security Management.	110

Chapter 8: Users and Groups..... 112

Users and Groups OverviewUsers and Groups.	112
Default Groups.	113
Administrator Group.	113
Everyone Group.	113
Operator Group.	114
Understanding User Accounts.	114
Default Administrator.	114
Domain Administrator.	115
Application Client Administrator.	115
User.	116
Managing Users.	116
Creating Native UsersCreating UsersCreating Users.	117
Editing General Properties of Native Users.	117
Assigning Native Users to Native Groups.	118
Assigning LDAP Users to Native Groups.	118

Enabling and Disabling User Accounts.	118
Deleting Native Users.	119
LDAP Users.	119
Unlocking a User Account.	119
Increasing System Memory for Many Users.	120
Viewing User Activity.	121
Managing Groups.	124
Adding a Native Group.	124
Editing Properties of a Native Group.	125
Moving a Native Group to Another Native Group.	125
Deleting a Native Group.	125
LDAP Groups.	126
Managing Operating System Profiles.	126
Operating System Profile Properties for the PowerCenter Integration Service	126
Operating System Profile Properties for the Data Integration Service.	128
Creating an Operating System Profile.	129
Editing an Operating System Profile.	130
Assigning a Default Operating System Profile to a User or Group.	131
Deleting an Operating System Profile	131
Working with Operating System Profiles in a Secure Domain.	131
Working with Operating System Profiles in a Domain with Kerberos Authentication.	132
Account Lockout.	133
Configuring Account Lockout.	133
Rules and Guidelines for Account Lockout.	133
Chapter 9: Privileges and Roles.....	135
Privileges and Roles Overview.	135
Privileges.	135
Roles.	137
Domain Privileges.	137
Security Administration Privilege Group.	138
Domain Administration Privilege Group.	139
Monitoring Privilege Group.	144
Tools Privilege Group.	145
Cloud Administration Privilege Group.	145
Analyst Service Privileges.	146
Content Management Service Privileges.	147
Data Integration Service Privileges.	147
Metadata Manager Service Privileges.	148
Catalog Privilege Group.	148
Load Privilege Group.	149
Model Privilege Group.	150
Security Privilege Group.	151

Model Repository Service Privileges.	151
PowerCenter Repository Service Privileges.	153
Tools Privilege Group.	153
Folders Privilege Group.	154
Design Objects Privilege Group.	155
Sources and Targets Privilege Group.	158
Run-time Objects Privilege Group.	160
Global Objects Privilege Group.	164
PowerExchange Listener Service Privileges.	166
PowerExchange Logger Service Privileges.	167
Scheduler Service Privileges.	168
Test Data Manager Service Privileges.	168
Administration Privilege Group.	169
Connections Privilege Group.	170
Data Domains Privilege Group.	170
Data Masking Privilege Group.	171
Data Subset Privilege Group.	172
Policies Privilege Group.	172
Projects Privilege Group.	173
Rules Privilege Group.	175
Data Generation Privilege Group.	176
Managing Roles.	176
System-Defined Roles.	177
Custom Roles.	179
Assigning Privileges and Roles to Users and Groups.	180
Inherited Privileges.	181
Assigning Privileges and Roles to a User or Group by Navigation.	181
Viewing Users with Privileges for a Service.	182
Troubleshooting Privileges and Roles.	182
Chapter 10: Permissions.....	184
Permissions Overview.	184
Types of Permissions.	185
Permission Search Filters.	186
Domain Object Permissions.	186
Permissions by Domain Object.	188
Permissions by User or Group.	189
Operating System Profile Permissions.	190
Connection Permissions.	191
Types of Connection Permissions.	192
Default Connection Permissions.	192
Assigning Permissions on a Connection.	192
Viewing Permission Details on a Connection.	193

Editing Permissions on a Connection.	193
Application and Application Object Permissions.	194
Types of Application and Application Object Permissions.	194
Assigning Permissions on an Application or Application Object.	194
Viewing Permission Details on an Application or Application Object.	195
Editing Permissions on an Application or Application Object.	195
Denying Permissions on an Application or Application Object.	196
SQL Data Service Permissions.	196
Types of SQL Data Service Permissions.	196
Assigning Permissions on an SQL Data Service.	197
Viewing Permission Details on an SQL Data Service.	197
Editing Permissions on an SQL Data Service.	197
Denying Permissions on an SQL Data Service.	198
Column Level Security.	198
Web Service Permissions.	200
Types of Web Service Permissions.	200
Assigning Permissions on a Web Service.	201
Viewing Permission Details on a Web Service.	201
Editing Permissions on a Web Service.	202
Chapter 11: Audit Reports.	203
Audit Reports Overview.	203
User Personal Information.	204
User Group Association.	204
Privileges.	205
Roles Association.	206
Domain Object Permission.	206
Selecting Users for an Audit Report.	207
Selecting Groups for an Audit Report	207
Selecting Roles for an Audit Report.	208
Appendix A: Command Line Privileges and Permissions.	209
infacmd as Commands.	209
infacmd dis Commands.	210
infacmd es commands.	211
infacmd ipc Commands.	211
infacmd isp Commands.	212
infacmd mrs Commands.	222
infacmd ms Commands.	225
infacmd oie Commands.	225
infacmd ps Commands.	225
infacmd pwx Commands.	226
infacmd rms Commands.	227

infacmd rtm Commands.	228
infacmd sch commands.	228
infacmd sql Commands.	229
infacmd wfs Commands.	230
pmcmd Commands.	230
pmrep Commands.	232
Appendix B: Custom Roles.....	238
Analyst Service Custom Role.	238
Metadata Manager Service Custom Roles.	239
Operator Custom Role.	240
PowerCenter Repository Service Custom Roles.	241
Test Data Manager Custom Roles.	242
Appendix C: Default List of Cipher Suites.....	247
Index.	249

Preface

The Informatica Security Guide contains information about security in the Informatica domain. It contains information that you need to manage security for the Informatica domain and the Informatica clients that connect to the domain. This book assumes that you have knowledge of the Informatica domain and the Informatica Administrator. It also assumes that you are familiar with the authentication servers and processes for your network.

Informatica Resources

Informatica Network

Informatica Network hosts Informatica Global Customer Support, the Informatica Knowledge Base, and other product resources. To access Informatica Network, visit <https://network.informatica.com>.

As a member, you can:

- Access all of your Informatica resources in one place.
- Search the Knowledge Base for product resources, including documentation, FAQs, and best practices.
- View product availability information.
- Review your support cases.
- Find your local Informatica User Group Network and collaborate with your peers.

Informatica Knowledge Base

Use the Informatica Knowledge Base to search Informatica Network for product resources such as documentation, how-to articles, best practices, and PAMs.

To access the Knowledge Base, visit <https://kb.informatica.com>. If you have questions, comments, or ideas about the Knowledge Base, contact the Informatica Knowledge Base team at KB_Feedback@informatica.com.

Informatica Documentation

To get the latest documentation for your product, browse the Informatica Knowledge Base at https://kb.informatica.com/_layouts/ProductDocumentation/Page/ProductDocumentSearch.aspx.

If you have questions, comments, or ideas about this documentation, contact the Informatica Documentation team through email at infa_documentation@informatica.com.

Informatica Product Availability Matrixes

Product Availability Matrixes (PAMs) indicate the versions of operating systems, databases, and other types of data sources and targets that a product release supports. If you are an Informatica Network member, you can access PAMs at

<https://network.informatica.com/community/informatica-network/product-availability-matrices>.

Informatica Velocity

Informatica Velocity is a collection of tips and best practices developed by Informatica Professional Services. Developed from the real-world experience of hundreds of data management projects, Informatica Velocity represents the collective knowledge of our consultants who have worked with organizations from around the world to plan, develop, deploy, and maintain successful data management solutions.

If you are an Informatica Network member, you can access Informatica Velocity resources at

<http://velocity.informatica.com>.

If you have questions, comments, or ideas about Informatica Velocity, contact Informatica Professional Services at ips@informatica.com.

Informatica Marketplace

The Informatica Marketplace is a forum where you can find solutions that augment, extend, or enhance your Informatica implementations. By leveraging any of the hundreds of solutions from Informatica developers and partners, you can improve your productivity and speed up time to implementation on your projects. You can access Informatica Marketplace at <https://marketplace.informatica.com>.

Informatica Global Customer Support

You can contact a Global Support Center by telephone or through Online Support on Informatica Network.

To find your local Informatica Global Customer Support telephone number, visit the Informatica website at the following link:

<http://www.informatica.com/us/services-and-training/support-services/global-support-centers>.

If you are an Informatica Network member, you can use Online Support at <http://network.informatica.com>.

CHAPTER 1

Introduction to Informatica Security

This chapter includes the following topics:

- [Overview of Informatica Security, 13](#)
- [Infrastructure Security, 14](#)
- [Operational Security, 16](#)
- [Domain Configuration Repository, 16](#)
- [Security Domain, 17](#)

Overview of Informatica Security

You can secure the Informatica domain to protect from threats from inside and outside the network on which the domain runs.

Security for the Informatica domain includes the following types of security:

Infrastructure Security

Infrastructure security protects the Informatica domain against unauthorized access to or modification of services and resources in the Informatica domain. Infrastructure security includes the following aspects:

- Protection of data transmitted and stored within the Informatica domain
- Authentication of users and services connecting to the Informatica domain
- Security of connections for external components, including client applications and relational databases for repositories, sources, and targets.

Operational Security

Operational security controls access to the data and services in the Informatica domain. Operational security includes the following aspects:

- Setting restrictions to user access to data and metadata based on the role of the user in the organization
- Setting restrictions to user ability to perform operations within the Informatica domain based on the user role in the organization

Informatica stores the domain configuration information and the list of users authorized to access the domain in the domain configuration repository. The domain configuration repository also contains the groups, roles, privileges, and permissions that are assigned to each user in the Informatica domain.

Informatica organizes the list of users by security domains. A security domain contains a collection of user accounts. A domain can have multiple security domains.

Infrastructure Security

Infrastructure security includes user and service authentication, secure communication within the domain, and secure data storage.

Authentication

The Service Manager authenticates the services that run in the domain and the users who log in to the Informatica client tools.

You can configure the Informatica domain to use the following types of authentication:

Native Authentication

Native authentication is a mode of authentication available only for user accounts in the Informatica domain. When the Informatica domain uses native authentication, the Service Manager stores user credentials and privileges in the domain configuration repository and performs all user authentication within the Informatica domain.

If the Informatica domain uses native authentication, by default, the domain has a Native security domain and all user accounts belong to the Native security domain.

Informatica uses user name and passwords to authenticate users and services in the Informatica domain.

Lightweight Directory Access Protocol (LDAP) Authentication

LDAP is a software protocol for accessing users and resources on a network. If the Informatica domain uses LDAP authentication, the user accounts and credentials are stored in the LDAP directory service. The user privileges and permissions are stored in the domain configuration repository. You must periodically synchronize the user accounts in the domain configuration repository with the user accounts in the LDAP directory service.

Informatica uses user name and passwords to authenticate Informatica users and services in the Informatica domain.

Kerberos Authentication

Kerberos is a network authentication protocol which uses tickets to authenticate users and services in a network. When the Informatica domain uses Kerberos authentication, the user accounts and credentials are stored in the Kerberos principal database, which can be an LDAP directory service. The user privileges and permissions are stored in the domain configuration repository. You must periodically synchronize the user accounts in the domain configuration repository with the user accounts in the Kerberos principal database.

Informatica uses the Kerberos tickets to authenticate Informatica users and services in the Informatica domain.

SAML-based Single Sign-on

Security Assertion Markup Language (SAML) is an XML-based data format for exchanging authentication and authorization information between a service provider and an identity provider. You can configure SAML-based single sign-on for the Administrator tool, the Analyst tool, and the Monitoring tool web applications.

In an Informatica domain, the Informatica web application is the service provider, and Microsoft Active Directory Federation Services (AD FS) is the identity provider. The accounts and credentials for Informatica web application users are stored in Microsoft Active Directory. You import accounts from Active Directory into a security domain within the Informatica domain. You must periodically synchronize the user accounts in the security domain with the user accounts in the Active Directory directory service.

Note that you cannot enable SAML-based single sign-on in an Informatica domain configured to use Kerberos authentication.

Secure Domain Communication

The Informatica domain has various options to secure the data and metadata that are transmitted between the Service Manager and services in the domain and the client applications. Informatica uses the TCP/IP and HTTP protocols to communicate between components in the domain and uses SSL certificates to secure the communication between services and the Service Manager in the domain.

The SSL/TLS protocol uses public key cryptography to encrypt and decrypt network traffic. The public key used to encrypt and decrypt traffic is stored in an SSL certificate that can be self-signed or signed. A self-signed certificate is signed by the creator of the certificate. Because the identity of the signer is not verified, a self-signed certificate is less secure than a signed certificate. A signed certificate is an SSL certificate that has the identity of the person who requested the certificate verified by a certificate authority (CA). Informatica recommends CA signed certificates for a higher level of security.

A keystore contains private keys and certificates. It is used to provide a credential. A truststore contains the certificate of trusted SSL/TLS servers. It is used to verify a credential.

To secure connections in the domain, Informatica requires keystores and truststores in PEM and JKS formats. You can use the following programs to create the required files:

keytool

Use keytool to create an SSL certificate or a Certificate Signing Request (CSR) as well as keystores and truststores in JKS format.

For more information about keytool, see the documentation on the following website:

<http://docs.oracle.com/javase/7/docs/technotes/tools/windows/keytool.html>

OpenSSL

You can use OpenSSL to create an SSL certificate or CSR as well as convert a keystore in JKS format to PEM format.

For more information about OpenSSL, see the documentation on the following website:

<https://www.openssl.org/docs/>

The type of connection that you secure determines the files required.

Secure Data Storage

Informatica encrypts sensitive data, such as passwords and secure connection parameters, before it stores the data in the domain configuration repository. Informatica also saves sensitive files, such as configuration files, in a secure directory.

Operational Security

You can assign privileges, roles, and permissions to users or groups of users to manage the level of access users and groups can have and the scope of the actions that users and groups can perform in the domain.

You can use the following methods to manage user and group access in the domain:

Privileges

Privileges determine the actions that users can perform in the Informatica client tools. You can assign a set of privileges to a user to restrict access to the services available in the domain. You can also assign privileges to a group to allow all users in the group the same access to services.

Roles

A role is a set of privileges that you can assign to users or groups. You can use roles to more easily manage assignments of privileges to users. You can create a role with limited privileges and assign it to users and groups that have restricted access to domain services. Or you can create roles with related privileges to assign to users and groups that require the same level of access.

Permissions

Permissions define the level of access that users have to an object. A user who has the privilege to perform a certain action might require permission to perform the action on a particular object. For example, to manage an application service, a user must have the privilege to manage services and permission on the specific application service.

Default Administrator Group

The Informatica domain has a system-defined Administrator group that includes all privileges and permissions for a service. Any user account that you add to the Administrator group has privileges and permissions on all services and objects in the domain. When you install Informatica services, the installer creates a user account that belongs to the Administrator group. You can use the default Administrator account to initially log in to the Administrator tool.

Domain Configuration Repository

The domain configuration repository contains information about the domain configuration and user privileges and permissions.

If the Informatica domain uses native user authentication, the domain configuration repository also contains the user credentials. If the domain uses LDAP or Kerberos authentication, the domain configuration repository does not contain the user credentials. All LDAP and Kerberos user credentials are stored outside the Informatica domain, in the LDAP directory service or Kerberos principal database.

When you create the Informatica domain during installation, the installer creates a domain configuration repository in a relational database. You must specify the database in which to create the domain configuration repository. You can create the repository on a database secured with the SSL protocol.

Security Domain

A security domain is a collection of user accounts and groups in the Informatica domain.

The Informatica domain can have the following types of security domains:

Native Security Domain

The Native security domain contains the users and groups created and managed in the Administrator tool. Informatica stores all credentials for user accounts in the Native security domain in the domain configuration repository. By default, the Native security domain is created during installation. After installation, you cannot create additional Native security domains or delete the Native security domain.

If the Informatica domain uses Kerberos authentication, the domain does not use the Native security domain.

LDAP Security Domain

An LDAP security domain contains users and groups imported from an LDAP directory service. If the Informatica domain uses LDAP or Kerberos authentication, you can create an LDAP security domain and add users and groups that you import from the LDAP directory service.

When you install Informatica services and create a domain that uses native or LDAP authentication, the installer creates the Native security domain but does not create an LDAP security domain. You can create LDAP security domains after installation.

When you install Informatica services and create a domain that uses Kerberos authentication, the installer creates the following LDAP security domains:

- Internal security domain. The installer creates an LDAP security domain with the name *_infalInternalNamespace*. The *_infalInternalNamespace* security domain contains the default administrator user account that you create during installation. After installation, you cannot add users to the *_infalInternalNamespace* security domain or delete the security domain.
- User realm security domain. The installer creates an empty LDAP security domain gives it the same name as the Kerberos user realm you specify during installation. After installation, you can import users from the Kerberos principal database into the user realm security domain. You cannot delete the user realm security domain.

When you run command line programs in a domain that uses Kerberos authentication, the security domain option defaults to the user realm security domain created during installation.

You create and manage LDAP security domains the same way, whether the Informatica domain uses LDAP authentication or Kerberos authentication.

CHAPTER 2

User Authentication

This chapter includes the following topics:

- [User Authentication Overview, 18](#)
- [Native User Authentication, 19](#)
- [LDAP User Authentication, 19](#)
- [Kerberos Authentication, 20](#)
- [SAML-based Single Sign-on for Informatica Web Applications, 20](#)

User Authentication Overview

User authentication in the Informatica domain depends on the type of authentication that you configure when you install the Informatica services.

The Informatica domain can use the following types of authentication to authenticate users in the Informatica domain:

- Native user authentication
- LDAP user authentication
- Kerberos network authentication
- Security Assertion Markup Language (SAML)-based single sign-on

Native user accounts are stored in the Informatica domain and can only be used within the Informatica domain.

LDAP and Kerberos user accounts are stored in an LDAP directory service and are shared by applications within the enterprise.

SAML-based single sign-on authenticates users against account credentials stored in Microsoft Active Directory. Accounts are imported from Active Directory into a security domain within the Informatica domain.

You can select the type of authentication to use in the Informatica domain during installation. If you enable Kerberos authentication during installation, you must configure the Informatica domain to work with the Kerberos key distribution center (KDC). You must create the service principal names (SPN) required by the Informatica domain in the Kerberos principal database. The Kerberos principal database can be an LDAP directory service. You must also create keytab files for the SPNs and store it in the Informatica directory as required by the Informatica domain.

If you do not enable Kerberos authentication during installation, the installer configures the Informatica domain to use native authentication. After installation, you can set up a connection to an LDAP server and configure the Informatica domain to use LDAP authentication in addition to native authentication.

You can use native authentication and LDAP authentication together in the Informatica domain. The Service Manager authenticates the users based on the security domain. If a user belongs to the native security domain, the Service Manager authenticates the user in the domain configuration repository. If the user belongs to an LDAP security domain, the Service Manager passes the user name and password to the LDAP server for authentication.

You cannot use native authentication with Kerberos authentication. If the Informatica domain uses Kerberos authentication, all user accounts must be in LDAP security domains. The Kerberos server authenticates a user account when the user logs in to the network. The Informatica client applications use the credentials from the network login to authenticate users in the Informatica domain. Native groups and roles are still supported.

You can enable SAML-based single sign-on for Informatica web applications during installation, or after installation. However you must complete all required set up tasks before enabling SAML-based single sign-on. You cannot enable SAML-based single sign-on in an Informatica domain configured to use Kerberos authentication.

Native User Authentication

If the Informatica domain uses native authentication, the Service Manager stores all user account information and performs all user authentication within the Informatica domain. When a user logs in, the Service Manager uses the native security domain to authenticate the user name and password.

If you do not configure the Informatica domain to use Kerberos network authentication, the Informatica domain contains a native security domain by default. The native security domain is created at installation and cannot be deleted. An Informatica domain can have only one native security domain. You create and maintain user accounts in the native security domain in the Administrator tool. The Service Manager stores details about the user accounts, including the user credentials and privileges, in the domain configuration repository.

LDAP User Authentication

You can configure the Informatica domain to allow users in an LDAP directory service to log in to Informatica client applications. The Informatica domain can use LDAP user authentication in addition to native user authentication.

To enable the Informatica domain to use LDAP user authentication, you must set up a connection to an LDAP server and specify the users and groups from the LDAP directory service that can have access to the Informatica domain. You can use the Administrator tool to set up the connection to the LDAP server.

When you synchronize the LDAP security domains with the LDAP directory service, the Service Manager imports the list of LDAP user accounts with access to the Informatica domain into the LDAP security domains. When you assign privileges and permissions to users in LDAP security domains, the Service Manager stores the information in the domain configuration repository. The Service Manager does not store the user credentials in the domain configuration repository.

When a user logs in, the Service Manager passes the user name and password to the LDAP server for authentication.

Note: The Service Manager requires that LDAP users log in to a client application with a password even though an LDAP directory service may allow a blank password for anonymous login mode.

Kerberos Authentication

You can configure the Informatica domain to use Kerberos network authentication to authenticate users and services on a network.

Kerberos is a network authentication protocol which uses tickets to authenticate access to services and nodes in a network. Kerberos uses a Key Distribution Center (KDC) to validate the identities of users and services and to grant tickets to authenticated user and service accounts. In the Kerberos protocol, users and services are known as principals. The KDC has a database of principals and their associated secret keys that are used as proof of identity. Kerberos can use an LDAP directory service as a principal database.

To use Kerberos authentication, you must install and run the Informatica domain on a network that uses Kerberos network authentication. Informatica can run on a network that uses Kerberos authentication with Microsoft Active Directory service as the principal database.

Informatica does not support cross or multi-realm Kerberos authentication. The server host, client machines, and Kerberos authentication server must be in the same realm.

The Informatica domain requires keytab files to authenticate nodes and services in the domain without transmitting passwords over the network. The keytab files contain the service principal names (SPN) and associated encrypted keys. Create the keytab files before you create nodes and services in the Informatica domain.

SAML-based Single Sign-on for Informatica Web Applications

You can configure an Informatica domain to allow users to use SAML-based single sign-on (SSO) to log into the Administrator tool, the Analyst tool, and the Monitoring tool web applications.

Security Assertion Markup Language (SAML) is an XML-based data format for exchanging authentication and authorization information between a service provider and an identity provider. In an Informatica domain, the Informatica web application is the service provider. Microsoft Active Directory Federation Services (AD FS) 2.0 is the identity provider, which authenticates web application users with your organization's Active Directory identity store.

To enable the Informatica domain to use SAML-based single sign-on, you must create an LDAP security domain for Informatica web application user accounts, and then import the users into the domain from Active Directory. You can use the Administrator tool to set up the connection to the Active Directory server, and then import users into the security domain.

When a user logs into an Informatica web application, the application sends a SAML authentication request to AD FS. AD FS authenticates the user's credentials against the user account information in Active Directory, and then returns a SAML assertion token containing security-related information about the user to the web application.

You configure AD FS to issue SAML tokens used to authenticate Informatica web application users. You must also export the Identity Provider Assertion Signing Certificate from AD FS, and then import the certificate into the Informatica default truststore file on each gateway node in the domain.

CHAPTER 3

LDAP Security Domains

This chapter includes the following topics:

- [LDAP Security Domains Overview, 21](#)
- [Setting Up an LDAP Security Domain, 22](#)
- [Deleting an LDAP Security Domain, 27](#)

LDAP Security Domains Overview

An LDAP security domain contains a set of users and groups that are imported from an LDAP directory service. You must create an LDAP security domain if you use LDAP user authentication or Kerberos network authentication.

Configure the LDAP security domains to store the list of users from an LDAP directory service that you want to allow access to the Informatica domain and client applications. The LDAP security domain does not store user account credentials. When a user logs in to an Informatica client, the Service Manager verifies that the user account is in a security domain. If the user account belongs to an LDAP security domain, the Service Manager authenticates the user with the LDAP directory service.

When you install Informatica services and you do not enable Kerberos authentication, the Informatica installer creates the native security domain by default. After installation, you can add users and groups to the native security domain. If you have users in an LDAP directory service that you want to give access to Informatica client applications, you can set up LDAP security domains in addition to the native security domain. Configure a connection to the LDAP server and import the users and groups into the LDAP security domains.

When you install Informatica services and enable Kerberos authentication, the Informatica installer creates an LDAP security domain with the name of the Kerberos realm that you specify during installation. After installation, you can configure a connection to the LDAP server and import users and groups from the LDAP directory service into the LDAP security domain. If you use Kerberos authentication, you cannot use the Native security domain.

Setting Up an LDAP Security Domain

You can create an LDAP security domain for user accounts that you import from an LDAP directory service. To organize different groups of users, you can create multiple LDAP security domains.

You create and manage LDAP users and groups in the LDAP directory service. Set up a connection to the LDAP server and use search filters to specify the users and groups that can have access to the Informatica domain. Then import the user accounts into LDAP security domains. If the LDAP server uses the SSL protocol, you must also specify the location of the SSL certificate.

You can import users from the following LDAP directory services:

- IBM Tivoli Directory Server
- Microsoft Active Directory

Note: If you use Kerberos authentication, you can only import users from Microsoft Active Directory.

- Novell eDirectory
- OpenLDAP
- Sun Java System Directory Server

After you import users into an LDAP security domain, you can assign roles, privileges, and permissions to the users. You can assign LDAP user accounts to native groups to organize them based on their roles in the Informatica domain.

You cannot use the Administrator tool to create, edit, or delete users and groups in an LDAP security domain. You must make changes to LDAP users and groups in the LDAP directory service, then synchronize the LDAP security domain with the LDAP directory service.

Use the LDAP Configuration dialog box to set up the connection to the LDAP directory service and create the LDAP security domain. You can also use the LDAP Configuration dialog box to set up a synchronization schedule.

To set up the LDAP security domain, perform the following steps:

1. Set up the connection to the LDAP directory service.
2. Configure a security domain.
3. Schedule the synchronization times.

Step 1. Set Up the Connection to the LDAP Server

Configure the connection to the LDAP server that contains the directory service from which you want to import the user accounts for the Informatica domain.

When you configure the connection to the LDAP server, indicate that the Service Manager must ignore the case-sensitivity of the distinguished name attributes of the LDAP user accounts when it assigns users to groups in the Informatica domain. If the Service Manager does not ignore case sensitivity, the Service Manager might not assign all the users that belong to a group.

If the LDAP server uses SSL, you must import the certificate into the `cacerts` truststore file on every gateway node within the Informatica domain. See [“Using a Self-Signed SSL Certificate” on page 26](#) for details.

To set up a connection to the LDAP directory service, perform the following tasks:

1. In the Administrator tool, click the **Security** tab.
2. Click the **Actions** menu and select **LDAP Configuration**.
3. In the **LDAP Configuration** dialog box, click the **LDAP Connectivity** tab.

4. Configure the connection properties for the LDAP server.

You might need to consult the LDAP administrator to get the information about the LDAP server.

The following table describes the LDAP server configuration properties:

Property	Description
Server name	Host name or IP address of the machine hosting the LDAP directory service.
Port	Listening port for the LDAP server. This is the port number to communicate with the LDAP directory service. Typically, the LDAP server port number is 389. If the LDAP server uses SSL, the LDAP server port number is 636. The maximum port number is 65535.
LDAP Directory Service	Type of LDAP directory service. Note: If you use Kerberos authentication, you must select Microsoft Active Directory.
Name	Distinguished name (DN) for the principal user. The user name often consists of a common name (CN), an organization (O), and a country (C). The principal user name is an administrative user with access to the directory. Specify a user that has permission to read other user entries in the LDAP directory service. Leave blank for anonymous login. For more information, see the documentation for the LDAP directory service.
Password	Password for the principal user. Leave blank for anonymous login. Not available if you use Kerberos authentication.
Use SSL Certificate	Indicates that the LDAP server uses the Secure Socket Layer (SSL) protocol.
Trust LDAP Certificate	Determines whether the Service Manager can trust the SSL certificate of the LDAP server. If selected, the Service Manager connects to the LDAP server without verifying the SSL certificate. If not selected, the Service Manager verifies that the SSL certificate is signed by a certificate authority before connecting to the LDAP server. To enable the Service Manager to recognize a self-signed certificate as valid, specify the truststore file and password to use.
Not Case Sensitive	Indicates that the Service Manager must ignore case sensitivity for distinguished name attributes when assigning users to groups. Enable this option.
Group Membership Attribute	Name of the attribute that contains group membership information for a user. This is the attribute in the LDAP group object that contains the DNs of the users or groups who are members of a group. For example, <i>member</i> or <i>memberof</i> .
Maximum Size	Maximum number of user accounts to import into a security domain. For example, if the value is set to 100, you can import a maximum of 100 user accounts into the security domain. If the number of user to be imported exceeds the value for this property, the Service Manager generates an error message and does not import any user. Set this property to a higher value if you have many users to import. Default is 1000.

5. Click Test Connection to verify that the connection to the LDAP server is valid.

Step 2. Configure a Security Domain

Create a security domain for each set of user accounts and groups you want to import from the LDAP directory service. Set up search bases and filters to define the set of user accounts and groups to include in a

security domain. The Service Manager uses the user search bases and filters to import user accounts and the group search bases and filters to import groups. The Service Manager imports groups and the list of users that belong to the groups. It imports the groups that are included in the group filter and the user accounts that are included in the user filter.

The names of users and groups to be imported from the LDAP directory service must conform to the same rules as the names of native users and groups. The Service Manager does not import LDAP users or groups if names do not conform to the rules of native user and group names.

Note: Unlike native user names, LDAP user names can be case-sensitive.

When you set up the LDAP directory service, you can use different attributes for the unique ID (UID). The Service Manager requires a particular UID to identify users in each LDAP directory service. Before you configure the security domain, verify that the LDAP directory service uses the required UID.

The following table lists the required UID for each LDAP directory service:

LDAP Directory Service	UID
IBM Tivoli Directory Server	uid
Microsoft Active Directory	sAMAccountName
Novell eDirectory	uid
OpenLDAP	uid
Sun Java System Directory Server	uid

The Service Manager does not import the LDAP attribute that indicates that a user account is enabled or disabled. You must enable or disable an LDAP user account in the Administrator tool. The status of the user account in the LDAP directory service affects user authentication in application clients. For example, a user account is enabled in the Informatica domain but disabled in the LDAP directory service. If the LDAP directory service allows disabled user accounts to log in, then the user can log in to application clients. If the LDAP directory service does not allow disabled user accounts to log in, then the user cannot log in to application clients.

Note: If you modify the LDAP connection properties to connect to a different LDAP server, the Service Manager does not delete the existing security domains. You must ensure that the LDAP security domains are correct for the new LDAP server. Modify the user and group filters in the security domains or create additional security domains so that the Service Manager correctly imports the users and groups that you want to use in the Informatica domain.

To configure an LDAP security domain, perform the following steps:

1. In the Administrator tool, click the **Security** tab.
2. Click the **Actions** menu and select **LDAP Configuration**.
3. In the **LDAP Configuration** dialog box, click the **Security Domains** tab.
4. Click **Add**.
5. Use LDAP query syntax to create filters to specify the users and groups to be included in the security domain you are creating.

You might need to consult the LDAP administrator to get the information about the users and groups available in the LDAP directory service.

The following table describes the filter properties that you can set for a security domain:

Property	Description
Security Domain	Name of the LDAP security domain. The name is not case sensitive and must be unique within the domain. It cannot exceed 128 characters or contain the following special characters: , + / < > @ ; \ % ? The name can contain an ASCII space character except for the first and last character. All other space characters are not allowed.
User search base	Distinguished name (DN) of the entry that serves as the starting point to search for user names in the LDAP directory service. The search finds an object in the directory according to the path in the distinguished name of the object. For example, in Microsoft Active Directory, the distinguished name of a user object might be cn=UserName,ou=OrganizationalUnit,dc=DomainName, where the series of relative distinguished names denoted by dc=DomainName identifies the DNS domain of the object.
User filter	An LDAP query string that specifies the criteria for searching for users in the directory service. The filter can specify attribute types, assertion values, and matching criteria. For example: (objectclass=*) searches all objects. (&(objectClass=user)(!(cn=susan))) searches all user objects except "susan." For more information about search filters, see the documentation for the LDAP directory service.
Group search base	Distinguished name (DN) of the entry that serves as the starting point to search for group names in the LDAP directory service.
Group filter	An LDAP query string that specifies the criteria for searching for groups in the directory service.

- Click **Preview** to view a subset of the list of users and groups that fall within the filter parameters.

If the preview does not display the correct set of users and groups, modify the user and group filters and search bases to get the correct users and groups.

- To add another LDAP security domain, repeat steps [4](#) through [6](#).

- To immediately synchronize the users and groups in the security domains with the users and groups in the LDAP directory service, click **Synchronize Now**.

The Service Manager synchronizes the users in all the LDAP security domains with the users in the LDAP directory service. The time it takes for the synchronization process to complete depends on the number of users and groups to be imported.

- Click **OK** to save the security domains.

Step 3. Schedule the Synchronization Times

You can set up a schedule for the Service Manager to periodically synchronize the list of users and groups in the LDAP security domain with the list of users and groups in the LDAP directory service.

Important: Before you start the synchronization process, verify that the /etc/hosts file contains an entry for the host name of the LDAP server. If the Service Manager cannot resolve the host name for the LDAP server, the user synchronization can fail.

During synchronization, the Service Manager imports users and groups from the LDAP directory service. The Service Manager deletes any user or group from the LDAP security domain that is no longer included in the search filters used for the import.

By default, the Service Manager does not have a scheduled time to synchronize with the LDAP directory service. To ensure that the list of users and groups in the LDAP security domains is accurate, you can schedule the times during the day when the Service Manager synchronizes the LDAP security domains. The Service Manager synchronizes the LDAP security domains with the LDAP directory service every day at the times you set.

Note: During synchronization, the Service Manager locks the user account that it synchronizes. When the user account is locked, the Service Manager cannot authenticate the user account. Users might not be able to log in to application clients. If users are logged in to application clients when synchronization starts, the users might not be able to perform tasks. The duration of the synchronization process depends on the number of users and groups to be synchronized. To avoid usage disruption, synchronize the security domains during times when most users are not logged in. To synchronize more than 100 users or groups, enable paging on the LDAP directory service before you run the synchronization. If you do not enable paging on the LDAP directory service, the synchronization can fail.

To set up a schedule to synchronize the LDAP security domains with the LDAP directory service, perform the following steps:

1. In the Administrator tool, click the **Security** tab.
2. Click the **Actions** menu and select **LDAP Configuration**.
3. In the **LDAP Configuration** dialog box, click the **Schedule** tab.
4. Click the **Add** button (+) to add a time.

The synchronization schedule uses a 24-hour time format.

You can add as many synchronization times in the day as you require. If the list of users and groups in the LDAP directory service changes often, you can schedule the Service Manager to synchronize multiple times a day.

5. To immediately synchronize the users and groups in the security domains with the users and groups in the LDAP directory service, click **Synchronize Now**.
6. Click **OK** to save the synchronization schedule.

Note: If you restart the Informatica domain before the Service Manager synchronizes with the LDAP directory service, the synchronization times that you added are lost.

Using Nested Groups in the LDAP Directory Service

An LDAP security domain can contain nested LDAP groups. The Service Manager can import nested groups that are created in the following manner:

- Create the groups under the same organizational units (OU).
- Set the relationship between the groups.

For example, you want to create a nested grouping where GroupB is a member of GroupA and GroupD is a member of GroupC.

1. Create GroupA, GroupB, GroupC, and GroupD within the same OU.
2. Edit GroupA, and add GroupB as a member.
3. Edit GroupC, and add GroupD as a member.

You cannot import nested LDAP groups into an LDAP security domain that are created in a different way.

Using a Self-Signed SSL Certificate

You can connect to an LDAP server that uses an SSL certificate signed by a certificate authority (CA). By default, the Service Manager does not connect to an LDAP server that uses a self-signed certificate.

To connect to an LDAP server that uses an SSL certificate, use the Java keytool key and certificate management utility to import the certificate into the `cacerts` truststore file on each gateway node in the domain. The `cacerts` truststore file is in the following directory on each node:

```
<Informatica installation directory>\java\jre\lib\security
```

The keytool utility is available in the following directory on each node:

```
<Informatica installation directory>\java\jre\bin
```

Restart the node after you import the certificate.

Deleting an LDAP Security Domain

To permanently prohibit users in an LDAP security domain from accessing application clients, you can delete the LDAP security domain. When you delete an LDAP security domain, the Service Manager deletes all user accounts and groups in the LDAP security domain from the domain configuration database.

1. In the LDAP Configuration dialog box, click the **Security Domains** tab.
The LDAP Configuration dialog box displays the list of security domains.
2. To ensure that you are deleting the correct security domain, click the security domain name to view the filter used to import the users and groups and verify that it is the security domain you want to delete.
3. Click the **Delete** button next to a security domain to delete the security domain.
4. Click **OK** to confirm that you want to delete the security domain.

CHAPTER 4

Kerberos Authentication

This chapter includes the following topics:

- [Kerberos Overview, 28](#)
- [How Kerberos Works in an Informatica Domain, 29](#)
- [Preparing to Enable Kerberos Authentication, 31](#)
- [Enabling Kerberos Authentication in a Domain, 45](#)
- [Enabling Kerberos on Informatica Nodes, 48](#)
- [Enabling User Accounts to Use Kerberos Authentication, 50](#)

Kerberos Overview

Kerberos is a computer network authentication protocol that enables Informatica nodes communicating over a network to connect to one another in a secure manner.

Kerberos authentication eliminates Informatica native accounts and removes the need for the domain to pass user credentials to an LDAP server. After you enable Kerberos authentication in a domain, Informatica clients use the Kerberos tickets created during the Windows authentication process to log in to the Informatica services running in the domain.

You can enable Kerberos authentication in a domain that runs on a Windows network. The network must use Microsoft Active Directory Domain Services (AD DS) as the Kerberos principal database.

To enable Kerberos authentication in an Informatica domain, perform the following steps:

Prepare to enable Kerberos authentication.

You must complete multiple tasks before you enable Kerberos authentication. The tasks you must complete include the following tasks:

- Create the Kerberos configuration file.
- Create accounts for Kerberos principal users in Active Directory.
- Generate the service principal name (SPN) and keytab formats.
- Create the keytab files used to authenticate users and services in the network.

Enable Kerberos authentication in the Informatica domain.

You can enable Kerberos authentication in an Informatica domain when you install the Informatica services, or you can enable Kerberos authentication after you install the services. If you do not enable Kerberos authentication during installation, you can use the Informatica command line programs to configure the domain to use Kerberos authentication.

Enable Kerberos authentication on Informatica nodes and client hosts.

After you enable Kerberos in the domain, copy the Kerberos configuration file to each node in the domain and to each Informatica client host. You also configure web browsers to access the Informatica web applications.

Enable Informatica users to use Kerberos authentication.

After you enable Kerberos authentication, import Informatica users from Active Directory into an LDAP security domain that contains the Kerberos user accounts. You must also migrate the groups, roles, privileges, and permissions of the native user accounts to the user accounts in the LDAP security domain.


How Kerberos Works in an Informatica Domain

In a domain configured to use Kerberos authentication, Informatica clients authenticate with Informatica nodes, web applications, and application services within the domain, without requiring passwords.

The Kerberos authentication protocol uses keytab files to authenticate Informatica clients with services that run within the domain, including node processes, web application processes, and Informatica application services. A *keytab* contains the *service principal name (SPN)* that identifies the service within the Kerberos realm. The keytab also contains the encrypted key assigned to the SPN in Active Directory.

When the KDC gives a service ticket to a client, it encrypts the ticket with the key assigned to the SPN. The same key is stored in a keytab file on the node on which the service runs. The requested service uses the key to decrypt the service ticket.

The following image illustrates the basic Kerberos authentication flow:



The following outline describes the basic Kerberos authentication flow:

1. An Informatica client user logs in to a network computer hosting an Informatica client.
2. The login request is directed to the *Authentication Server*, a component of the *Kerberos Key Distribution Center (KDC)*. The KDC is a network service with access to user account information that runs on each domain controller within the Active Directory domain.
3. The Authentication Server verifies that the user exists in the principal database, and then creates a Kerberos token called a *ticket-granting-ticket (TGT)* on the user's computer.
4. The user attempts to access a process or service within the Informatica domain through an Informatica client.
5. Informatica and the Kerberos libraries use the TGT to request a *service ticket* and *session key* for the requested service from the *Ticket Granting Server*, which also runs within the KDC.

For example, if the user accesses a Model Repository Service from the Informatica Developer client, the TGT requests a service ticket for the node on which the requested service runs. The TGT also requests a service ticket for the Model Repository Service.

6. Kerberos uses the service ticket to authenticates the client with the requested service. The service ticket is cached on the computer hosting the Informatica client, enabling the client to use the ticket while it remains valid. If the user shuts down and then restarts the Informatica client, the client reuses the same ticket to access processes and services within the Informatica domain.

Preparing to Enable Kerberos Authentication

You must complete multiple tasks to prepare to enable Kerberos authentication in an Informatica domain. The procedures you follow for each task depend on the service principal level at which you enable Kerberos.

Note: You cannot disable Kerberos authentication in a domain after you enable it. You also cannot switch the service principal level between the node level and the process level.

Step 1. Determine the Kerberos Service Principal Level

When you prepare to enable Kerberos authentication, you must determine the required service principal level. The required service principal level determines the procedures you must follow to prepare to enable Kerberos authentication in the domain.

You can enable Kerberos authentication at one of the following levels:

Node Level

If you use the domain for testing or development, and the domain does not require a high level of security, you can enable Kerberos at the node level. You can use a single service principal name and a single keytab file for the node and for all of the processes and services that run on the node. You must also create an SPN and a keytab file for the HTTP processes that run on the node.

Process Level

If you use the domain for production, and the domain requires a high level of security, you can set the service principal at the process level. You create a unique SPN and keytab file for each node and each process on the node. You must also create an SPN and a keytab file for the HTTP processes that run on the node.

Kerberos enabled at the process level provides the highest level of security, but might be difficult to manage in an Informatica domain that contains many nodes or has many services. In this scenario, you might want to enable Kerberos at the node level.

Step 2. Configure the Kerberos Configuration File

Set the properties required by Informatica in the Kerberos configuration file, and then copy the file to each node in the Informatica domain.

Kerberos stores configuration information in a file named *krb5.conf*. You must set the properties in the *krb5.conf* configuration file and then copy the file to every node in the Informatica domain.

1. Configure the following Kerberos library properties in the *libdefaults* section of the file.

The following table describes the properties to enter:

Property	Description
default_realm	Name of the Kerberos realm to which the Informatica domain services belong. The realm name must be in uppercase. The service realm name and the user realm name must be the same.
forwardable	Allows a service to delegate client user credentials to another service. The Informatica domain requires application services to authenticate the client user credentials with other services. Set to true.
default_tkt_enctypes	Encryption types for the session key included in ticket-granting tickets (TGT). Set this property only if session keys must use specific encryption types. Ensure that the Kerberos Key Distribution Center (KDC) supports the encryption type that you specify. Do not set this property to allow the Kerberos protocol to select the encryption type to use. If the node hosts or Informatica client hosts use 256-bit encryption, install the Java Cryptography Extension (JCE) unlimited strength policy files on all node hosts and Informatica client hosts to avoid authentication issues.
rdns	Determines whether reverse name lookup is used in addition to forward name lookup to canonicalize host names for use in service principal names. Set to false.
renew_lifetime	The default renewable lifetime for initial ticket requests.
ticket_lifetime	The default lifetime for initial ticket requests.
udp_preference_limit	Determines the protocol that Kerberos uses when it sends a message to the KDC. Set to 1 to use the TCP protocol if the domain experiences intermittent Kerberos authentication failures.

- Define each Kerberos realm in the *realms* section of the file.

The following example shows the entry for a Kerberos realm named COMPANY.COM.

```
[realms]
COMPANY.COM = {...}
```

- Enter the following realm properties inside the brackets for each Kerberos realm in the *realms* section of the file.

The following table describes the properties to enter:

Property	Description
admin_server	The name or IP address of the Kerberos administration server host. You can include an optional port number, separated from the host name by a colon. Default is 749.
kdc	The name or IP address of a host running the Key Distribution Center (KDC) for the realm. You can include an optional port number, separated from the host name by a colon. Default is 88.

The following example shows the entries for the COMPANY.COM Kerberos realm:

```
[realms]
COMPANY.COM = {
  admin_server = KDC01.COMPANY.COM:749
  kdc = KDC01.COMPANY.COM:88
}
```

4. Map the Windows domain to the Kerberos realm in the *domain_realm* section of the file. The Windows domain name must be all lowercase. The Kerberos realm name must be all uppercase.

The following example maps the company.com Windows domain to the COMPANY.COM Kerberos realm:

```
[domain_realm]
.company.com = COMPANY.COM
company.com = COMPANY.COM
```

5. Copy the configuration file to the following directory on every node in the domain:

<Informatica installation directory>\services\shared\security

The following example shows the content of a Kerberos configuration file with the required properties:

```
[libdefaults]
default_realm = COMPANY.COM
forwardable = true
rdns = false
renew_lifetime = 7d
ticket_lifetime = 24h
udp_preference_limit = 1

[realms]
KERBREALM.COM = {
  admin_server = KDC01.COMPANY.COM:749
  kdc = KDC01.COMPANY.COM:88
}

[domain_realm]
.company.com = COMPANY.COM
company.com = COMPANY.COM
```

For more information about the Kerberos configuration file, see the Kerberos network authentication documentation.

Step 3. Create Kerberos Principal Accounts in Active Directory

Create LDAP user accounts for the Kerberos principals in Active Directory. A Kerberos principal is a process, service, or user within the Kerberos realm.

If you set the `default_tkt_enctypes` property in the `krb5.conf` configuration file to the 128-bit or 256-bit AES encryption types, configure each account to use the corresponding encryption type in Active Directory.

The following image shows the AES 128-bit encryption option selected in the account properties dialog box for the `nodeuser01` user account in Active Directory:

The screenshot shows the 'nodeuser01 Properties' dialog box with the 'Account' tab selected. The 'User logon name' is 'nodeuser01' and the domain is '@COMPANY.COM'. The 'User logon name (pre-Windows 2000)' is 'RCW\' and the name is 'nodeuser01'. The 'Account options' section shows 'This account supports Kerberos AES 128 bit encryption' selected. The 'Account expires' section shows 'Never' selected.

Organization	Published Certificates	Member Of	Password Replication
Dial-in	Object	Security	Environment
Remote control	Remote Desktop Services Profile		COM+
General	Address	Account	Profile
Telephones		Delegation	

User logon name:
nodeuser01 @COMPANY.COM

User logon name (pre-Windows 2000):
RCW\ nodeuser01

Logon Hours... Log On To...

☐ Unlock account

Account options:

- ☐ Account is sensitive and cannot be delegated
- ☐ Use only Kerberos DES encryption types for this account
- ☒ This account supports Kerberos AES 128 bit encryption.
- ☐ This account supports Kerberos AES 256 bit encryption.
- ☐ Do not require Kerberos preauthentication

Account expires

☒ Never

☐ End of: Friday, November 17, 2017

OK Cancel Apply Help

The accounts that you create depend on whether you enable Kerberos at the node level or at the process level.

Accounts Required at Node Level

Create the LDAP user accounts required to enable Kerberos authentication at the node level in Active Directory.

Create the following Kerberos principal accounts in Active Directory if you enable Kerberos at the node level:

Node processes

Create an account for each node that runs in the domain.

HTTP process

Create an account for the Informatica web applications that run on a node in the domain. Web applications that run on a node might include the Administrator tool, Informatica Analyst, and Catalog Administrator. Create a single account that is shared by all of the web applications that run on the node.

Bind User Distinguished Name (DN)

Create an LDAP bind user account that you use to synchronize the LDAP security domain that contains Kerberos user accounts with Active Directory.

Accounts Required at Process Level

Create the LDAP user accounts required to enable Kerberos authentication at the process level in Active Directory.

Create the following Kerberos principal accounts in Active Directory if you enable Kerberos at the process level:

Node processes

Create an account for each node that runs in the domain.

HTTP processes

Create an account for the Informatica web applications that run on a node in the domain. Web applications that run on a node might include Informatica Analyst and Catalog Administrator. Create a single account that is shared by all of the web applications that run on the node.

Informatica Administrator service

Create an account for the Administrator tool on each gateway node in the domain.

Informatica application services

Create an account for every Informatica application service that runs on each node in the domain.

Bind User Distinguished Name (DN)

Create an LDAP user account that you use to synchronize the LDAP security domain that contains Kerberos user accounts with Active Directory.

Step 4. Generate the Service Principal Name and Keytab File Name Formats

Use the Informatica Kerberos SPN Format Generator utility to generate the service principal name (SPN) and keytab file name formats required to use Kerberos authentication. The Kerberos SPN Format Generator utility generates a text file named SPNKeytabFormat.txt that contains the correct format for the SPNs and keytab file names.

The SPN and keytab file name formats you generate depend on whether you enable Kerberos at the node level or at the process level.

Generate the Service Principal Name and Keytab File Name Formats at Node Level

Generate the formats for the SPNs and keytab file names required to enable Kerberos authentication at the node level.

The Informatica domain requires SPNs and keytab files for the following processes when you enable Kerberos authentication at the node level:

Node processes

Informatica requires an SPN and keytab file for every node in the domain. Kerberos uses the same service principal name and keytab to authenticate the Informatica application services that run on the node.

HTTP processes

Informatica requires an SPN and keytab file for the web applications that run on each node in the domain. Web applications that run on a node might include the Administrator tool, Informatica Analyst and Catalog Administrator. Kerberos uses the same service principal name to authenticate all of the web applications that run on the node.

1. On a Windows Informatica node host, go to the directory that contains the SPNFormatGenerator.bat batch file:

```
<Informatica installation directory>\tools\Kerberos
```

On a UNIX Informatica node host, go to the directory that contains the SPNFormatGenerator.sh shell file:

```
<Informatica installation directory>/tools/Kerberos
```


2. Run SPNFormatGenerator.bat or SPNFormatGenerator.sh.
3. Click **Next**.
4. Select **Node Level**.
5. Click **Next**.
6. Enter the properties required to generate the SPN and keytab file formats.

The following table describes the properties:

Prompt	Description
Domain Name	Name of the Informatica domain. The name must not exceed 128 characters and must be 7-bit ASCII. It cannot contain a space or any of the following characters: ` % * + ; " ? , < > \ /
Service Realm Name	Name of the Kerberos realm as defined in the Kerberos configuration file. The realm name must be in uppercase.
Node Name	Name of the Informatica node.
Node Host Name	Fully qualified name or the IP address of the node host. The node host name cannot contain the underscore (_) character. Note: Do not use <i>localhost</i> . The host name must explicitly identify the host.

7. To generate the SPN format for an additional node, click **+Node** and specify the node name and host name.

The following image shows the entries for multiple nodes in the InfaDomain domain in the SPN Format Generator utility:



8. Click **Next**.
The SPN Format Generator utility displays the path and file name of the file that contains the list of service principal names and keytab file names.
9. Click **Done** to exit the SPN Format Generator utility.

Generate the Service Principal Name and Keytab File Name Formats at Process Level

Generate the formats for the SPNs and keytab file names required to enable Kerberos authentication at the process level.

The Informatica domain requires SPNs and keytab files for the following processes and services when you enable Kerberos authentication at the process level:

Node processes

Informatica requires an SPN and keytab file for every node in the domain.

Informatica Administrator

Informatica requires an SPN and keytab file for the Administrator tool for every gateway node in the domain.

HTTP processes

Informatica requires an SPN and keytab file for the web applications that run on a node in the domain. Web applications that run on a node might include Informatica Analyst and Catalog Administrator.

Informatica application service processes

Informatica requires an SPN and keytab file for each Informatica application service that runs on every node in the domain.

1. On a Windows Informatica node host, go to the directory that contains the SPNFormatGenerator.bat batch file:

```
<Informatica installation directory>\tools\Kerberos
```

On a UNIX Informatica node host, go to the directory that contains the SPNFormatGenerator.sh shell file:

```
<Informatica installation directory>/tools/Kerberos
```

2. Run SPNFormatGenerator.bat or SPNFormatGenerator.sh.
3. Click **Next**.
4. Select **Process Level**.
5. Click **Next**.
6. Enter the properties required to generate the SPN and keytab file formats.

The following table describes the properties:

Prompt	Description
Domain Name	Name of the Informatica domain. The name must not exceed 128 characters and must be 7-bit ASCII. It cannot contain a space or any of the following characters: ` % * + ; " ? , < > \ /
Service Realm Name	Name of the Kerberos realm as defined in the Kerberos configuration file. The realm name must be in uppercase.
Node Name	Name of the Informatica node.
Node Host Name	Fully qualified name or the IP address of the node host. The node host name cannot contain the underscore (_) character. Note: Do not use <i>localhost</i> . The host name must explicitly identify the host.

7. To generate the SPN format for an Informatica application service that runs on a node, click **Service** after entering the node details.

Enter the name of the Informatica application service as shown in the Administrator tool. Complete this step for each Informatica application service that runs on each node in the domain.

8. To generate the SPN format for an additional node, click **+Node** and specify the node name and host name.

The following image shows the entries for multiple nodes and application services that run in the InfaDomain domain in the SPN Format Generator utility:

Informatica Kerberos SPN Format Generator

Authentication Parameters - Kerberos Authentication - Step 3 of 4

Specify the domain and Kerberos authentication parameters.

Domain name: InfaDomain

Service realm name: COMPANY.COM

Node name: node01

Node host name: JS001DEV

+Node +Service -Node

Service on node: MRS_dev

Service on node: DIS_dev

Node name: node02

Node host name: JS005DEV

Service on node: CMS_dev

? < Previous Next > Cancel

9. Click **Next**.

The SPN Format Generator utility displays the path and file name of the file that contains the list of service principal names and keytab file names.

10. Click **Done** to exit the SPN Format Generator utility.

Review the Service Principal Name and Keytab File Name Format Text File

After you generate the SPNKeytabFormat.txt file, you can review the file.

You use the information in the file to generate the keytab files, and to associate each SPN with the corresponding principal user account in Active Directory.

The SPNKeytabFormat.txt file contains the following information:

Entity Name

Identifies the node or service associated with the process.

Service Principal Name

Format for the SPN. The SPN is case sensitive.

The following table describes the SPN formats:

Keytab type	SPN Format
NODE_SPN	isp/<node name>/<domain name>@<REALM NAME>
NODE_AC_SPN	_AdminConsole/<node name>/<domain name>@<REALM NAME>
NODE_HTTP_SPN	HTTP/<node host name>@<REALM NAME> Note: The Kerberos SPN Format Generator validates the node host name. If the node host name is not valid, the utility does not generate an SPN. Instead, it displays the following message: Unable to resolve host name.
SERVICE_PROCESS_SPN	<application service name>/<node name>/<domain name>@<REALM NAME>

Keytab File Name

Format for the name of the keytab file to be created for the associated SPN. The keytab file name is case sensitive.

The following table describes the keytab file name formats:

Keytab Type	Keytab File Name
NODE_SPN	<node name>.keytab
NODE_AC_SPN	_AdminConsole.keytab
NODE_HTTP_SPN	webapp_http.keytab
SERVICE_PROCESS_SPN	<application service name>.keytab

Service Principals at Node Level

The following image shows the contents of the SPNKeytabFormat.txt file generated for service principals at the node level:

ENTITY_NAME	SPN	KEY_TAB_NAME	KEY_TAB_TYPE
node01	isp/node01/Infadomain@COMPANY.COM	node01.keytab	NODE_SPN
node01	HTTP/US001DEV.company.com@COMPANY.COM	webapp_http.keytab	NODE_HTTP_SPN
node02	isp/node02/Infadomain@COMPANY.COM	node02.keytab	NODE_SPN
node02	HTTP/US005DEV.company.com@COMPANY.COM	webapp_http.keytab	NODE_HTTP_SPN

Service Principals at Process Level

The following image shows the contents of the SPNKeytabFormat.txt file generated for service principals at the process level:

ENTITY_NAME	SPN	KEY_TAB_NAME	KEY_TAB_TYPE
node01	isp/node01/Infadomain@COMPANY.COM	node01.keytab	NODE_SPN
node01	_AdminConsole/node01/Infadomain@COMPANY.COM	_AdminConsole.keytab	NODE_AC_SPN
node01	HTTP/US001DEV.company.com@COMPANY.COM	webapp_http.keytab	NODE_HTTP_SPN
node02	isp/node02/Infadomain@COMPANY.COM	node02.keytab	NODE_SPN
node02	_AdminConsole/node02/Infadomain@COMPANY.COM	_AdminConsole.keytab	NODE_AC_SPN
node02	HTTP/US005DEV.company.com@COMPANY.COM	webapp_http.keytab	NODE_HTTP_SPN
MRS_dev:node01	MRS_dev/node01/Infadomain@COMPANY.COM	MRS_dev.keytab	SERVICE_PROCESS_SPN
DIS_dev:node01	DIS_dev/node01/Infadomain@COMPANY.COM	DIS_dev.keytab	SERVICE_PROCESS_SPN
CAT_dev:node02	CAT_dev/node02/Infadomain@COMPANY.COM	CAT_dev.keytab	SERVICE_PROCESS_SPN

Step 5. Generate the Keytab Files

Generate the keytab files used to authenticate Informatica users and services.

You use the Microsoft Windows Server ktpass utility to generate a keytab file for each user account you created in Active Directory. You must generate the keytab files on a member server or on a domain controller within the Active Directory domain. You cannot generate keytab files on a workstation operating system such as Microsoft Windows 7.

To use ktpass to generate a keytab file, run the following command:

```
ktpass.exe -out <keytab filename> -princ <service principal name> -mapuser <user account> [-pass <user account password>] -crypto <key types> -ptype <principal type>
```

The following table describes the command options:

Option	Description
-out	The file name of the Kerberos keytab file to generate as shown under the <code>KEY_TAB_NAME</code> column in the <code>SPNKeytabFormat.txt</code> file.
-princ	The service principal name displayed under the <code>SPN</code> column in the <code>SPNKeytabFormat.txt</code> file.
-mapuser	The Active Directory user account to associate with the SPN.
-pass	The password set in Active Directory for the Active Directory user account, if applicable.
-crypto	Specifies the key types generated in the keytab file. Set to all to use all supported cryptographic types.
-ptype	The principal type. Set to <code>KRB5_NT_PRINCIPAL</code> .

The keytab files you generate depends on whether you enable Kerberos at the node level or at the process level.

Generate the Keytab Files at Node Level

When you run ktpass to generate the keytab files at the node level, you associate each Kerberos principal user account with the corresponding SPN in Active Directory.

The following table shows the association between the Kerberos principal user accounts and the SPNs shown in the example `SPNKeytabFormat.txt` file:

User Account	Keytab Type	Service Principal Name
nodeuser01	NODE_SPN	isp/node01/InfraDomain/COMPANY.COM
httpuser01	NODE_HTTP_SPN	HTTP/US001DEV.company.com@COMPANY.COM
nodeuser02	NODE_SPN	isp/node02/InfraDomain/COMPANY.COM
httpuser02	NODE_HTTP_SPN	HTTP/US005DEV.company.com@COMPANY.COM

You also create a keytab for the LDAP bind user account that is used to access and search Active Directory during LDAP synchronization.

1. Create a keytab file for the Kerberos principal user account that you created for each node in Active Directory.

Copy the keytab file name from the `KEY_TAB_NAME` column in the `SPNKeytabFormat.txt` file. Copy the service principal name from the `SPN` column in the `SPNKeytabFormat.txt` file.

The following example creates a keytab file for a Kerberos principal user account named `nodeuser0`:

```
ktpass.exe -out node01.keytab -princ isp/node01/Infadomain/COMPANY.COM -mapuser
nodeuser01 -crypto all -ptype KRB5_NT_PRINCIPAL
```

2. Create a keytab file for each HTTP process Kerberos principal user account that you created in Active Directory.

Copy the keytab file name from the `KEY_TAB_NAME` column in the `SPNKeytabFormat.txt` file. Copy the service principal name from the `SPN` column in the `SPNKeytabFormat.txt` file.

The following example creates a keytab file for a Kerberos principal user account named `httpuser01`:

```
ktpass.exe -out webapp_http.keytab -princ HTTP/US001DEV.company.com@COMPANY.COM -mapuser
httpuser01 -crypto all -ptype KRB5_NT_PRINCIPAL
```

3. Create a keytab for the LDAP bind user account that is used to access and search Active Directory during LDAP synchronization.

Structure the value for the `-princ` option as `<principal name>@KERBEROS_REALM`. The file name of the keytab file must be `infa_ldapuser.keytab`.

The following example creates a keytab file for a service principal user account named `ldapuser`:

```
ktpass.exe -out infa_ldapuser.keytab -princ ldapuser@COMPANY.COM -mapuser ldapuser -
crypto all -ptype KRB5_NT_PRINCIPAL
```

Generate the Keytab Files at Process Level

When you run `ktpass` to generate the keytab files at the process level, you associate each Kerberos principal user account with the corresponding SPN in Active Directory.

The following table shows the association between the Kerberos principal user accounts and the SPNs shown in the example `SPNKeytabFormat.txt` file:

User Account	Keytab Type	Service Principal Name
nodeuser01	NODE_SPN	isp/node01/Infadomain/COMPANY.COM
admintooluser01	NODE_AC_SPN	_AdminConsole/node01/Infadomain@COMPANY.COM
httpuser01	NODE_HTTP_SPN	HTTP/US001DEV.company.com@COMPANY.COM
MRSdevuser01	SERVICE_PROCESS_SPN	MRS_dev/node01/Infadomain@COMPANY.COM
DISdevuser01	SERVICE_PROCESS_SPN	DIS_dev/node01/Infadomain@COMPANY.COM
nodeuser02	NODE_SPN	isp/node02/Infadomain/COMPANY.COM
admintooluser02	NODE_AC_SPN	_AdminConsole/node02/Infadomain@COMPANY.COM

User Account	Keytab Type	Service Principal Name
httpuser02	NODE_HTTP_SPN	HTTP/US005DEV.company.com@COMPANY.COM
CATdevuser01	SERVICE_PROCESS_SPN	CAT_dev/node02/Infadomain@COMPANY.COM

You also create a keytab for the LDAP bind user account that is used to access and search Active Directory during LDAP synchronization.

1. Create a keytab file for the Kerberos principal user account that you created for each node in Active Directory.

Copy the file name from the `KEY_TAB_NAME` column in the `SPNKeytabFormat.txt` file. Copy the service principal name from the `SPN` column in the `SPNKeytabFormat.txt` file.

The following example creates a keytab file for a Kerberos principal user account named `nodeuser01`:

```
ktpass.exe -out node01.keytab -princ isp/node01/Infadomain/COMPANY.COM -mapuser
nodeuser01 -crypto all -ptype KRB5_NT_PRINCIPAL
```

2. Create a keytab file for each HTTP process Kerberos principal user account that you created.

Copy the file name from the `KEY_TAB_NAME` column in the `SPNKeytabFormat.txt` file. Copy the service principal name from the `SPN` column in the `SPNKeytabFormat.txt` file.

The following example creates a keytab file for a Kerberos principal user account named `httpuser01`:

```
ktpass.exe -out webapp_http.keytab -princ HTTP/US001DEV.company.com@COMPANY.COM -mapuser
httpuser01 -crypto all -ptype KRB5_NT_PRINCIPAL
```

3. Create a keytab file for each Administrator tool Kerberos principal user account that you created.

Copy the file name from the `KEY_TAB_NAME` column in the `SPNKeytabFormat.txt` file. Copy the service principal name from the `SPN` column in the `SPNKeytabFormat.txt` file.

The following example creates a keytab file for a Kerberos principal user account named `admintooluser01`:

```
ktpass.exe -out _AdminConsole.keytab -princ _AdminConsole/node01/Infadomain@COMPANY.COM -
mapuser admintooluser01 -crypto all -ptype KRB5_NT_PRINCIPAL
```

4. Create a keytab file for each Informatica application service Kerberos principal user account that you created.

Copy the file name from the `KEY_TAB_NAME` column in the `SPNKeytabFormat.txt` file. Copy the service principal name from the `SPN` column in the `SPNKeytabFormat.txt` file.

The following example creates a keytab file for a service Kerberos principal user account named `MRSdevuser01`:

```
ktpass.exe -out MRS_dev.keytab -princ HTTP/US001DEV.company.com@COMPANY.COM -mapuser
MRSdevuser01 -crypto all -ptype KRB5_NT_PRINCIPAL
```

5. Create a keytab for the LDAP bind user account that is used to access and search Active Directory during LDAP synchronization.

Structure the value for the `-princ` option as `principal_name@KERBEROS_REALM`. The file name of the keytab file must be `infa_ldapuser.keytab`.

The following example creates a keytab file for a service principal user account named `ldapuser`:

```
ktpass.exe -out infa_ldapuser.keytab -princ ldapuser@COMPANY.COM -mapuser ldapuser -
crypto all -ptype KRB5_NT_PRINCIPAL
```

Verify the Service Principal Names and Keytab Files

You can use Kerberos utilities to verify that the SPNs and the keytab files are valid. You can also use the utilities to determine the status of the Kerberos Key Distribution Center (KDC).

You can use Kerberos utilities such as *kinit* and *klist* to view and verify the SPNs and keytab files. To use the utilities, ensure that the KRB5_CONFIG environment variable contains the path and file name of the Kerberos configuration file. For more information about running the Kerberos utilities, see the Kerberos documentation.

Use the following utilities to verify the SPNs and keytab files:

kinit

You can use the *kinit* utility to request a ticket-granting ticket (TGT) from the KDC and verify that a keytab file can be used to establish a Kerberos connection. If the keytab and specified SPN are valid, the command obtains a ticket, and then caches the ticket in the specified cache.

The *kinit* utility is available in the following directory on an Informatica node:

```
<Informatica installation directory>\java\jre\bin
```

To request a ticket-granting ticket for an SPN, run the following command:

```
kinit -c <cache name> -k -t <keytab file name> <service principal name>
```

The following output example shows the ticket-granting ticket created in the default cache for a specified keytab file and SPN:

```
Cache: \temp\krb
Using principal: isp/node01/Infadomain/COMPANY.COM
Using keytab: node01.keytab
Authenticated to Kerberos v5
```

klist

You can use the *klist* utility to list the Kerberos principals and keys in a keytab file. To list the keys in the keytab file and the time stamp for the keytab entry, run the following command:

```
klist -k -t <keytab file name>
```

The following output example shows the principals in a keytab file:

```
Keytab name: FILE:node01.keytab
KVNO Timestamp Principal
-----
3 12/31/16 19:00:00 MRS_dev/node01/Infadomain@COMPANY.COM
3 12/31/16 19:00:00 MRS_dev/node01/Infadomain@COMPANY.COM
3 12/31/16 19:00:00 MRS_dev/node01/Infadomain@COMPANY.COM
3 12/31/16 19:00:00 MRS_dev/node01/Infadomain@COMPANY.COM
```

Step 6. Enable Delegation for the Kerberos Principal User Accounts in Active Directory


Enable delegation for each Kerberos principal user account you created in Active Directory.

Delegated authentication happens when a user is authenticated with one service, and that service uses the credentials of the authenticated user to connect to another service. Because services in the Informatica domain need to connect to other services to complete an operation, the Informatica domain requires the delegation option to be enabled in Active Directory.

You must enable delegation for all accounts for all of the accounts you created, except for the LDAP bind user account that you use to access and search Active Directory during LDAP synchronization. Set delegation to **Trust this user for delegation to any service (Kerberos only)** in the Delegation tab in the properties dialog box for each user account.

Note: The Delegation tab is not available in the properties dialog box until you run ktpass to create the keytab files.

The following image shows the Delegation tab in the nodeuser01 account properties dialog box:



Enabling Kerberos Authentication in a Domain

You can enable Kerberos authentication in an Informatica domain when you install the Informatica services, or you can enable Kerberos authentication after you install the services.

For information on how to enable Kerberos authentication when you install the Informatica services, see the *Informatica Installation and Configuration Guide*.

If you do not enable Kerberos authentication during installation, follow the steps in this section to use the Informatica command line programs to enable Kerberos authentication after you install the services.

Step 1. Enable Kerberos Authentication in the Domain

Enable Kerberos on a gateway node within the domain.

You run the `infasetup switchToKerberosMode` command on a gateway node within the domain to change the authentication to Kerberos network authentication.

The `infasetup` command creates an administrator user account in an LDAP security domain with the name `_infalInternalNamespace`. Specify one of the user accounts you created in Active Directory as the administrator account. You use the account to log in to your Windows network after you enable Kerberos authentication in the domain.

1. Shut down the domain and all Informatica services. Shut down the services in the following order:

- Metadata Manager Service
- PowerCenter® Integration Service
- PowerCenter® Repository Service
- Content Management Service
- Analyst Service
- Data Integration Service
- Model Repository Service

2. At the command prompt on a gateway node, switch to the directory where the `infasetup` executable is located:

```
<Informatica installation directory>\isp\bin
```

3. Run the following command:

```
infasetup switchToKerberosMode -ad <administrator name> -srn <Kerberos realm name> -  
urn <Kerberos realm name> -spnSL <service principal level>
```

The following table describes the options and arguments for the `infasetup switchToKerberosMode` command:

Option	Argument	Description
-administratorName -ad	user_name	User name for the domain administrator account that is created when you configure Kerberos authentication. Specify the name of an account that exists in Active Directory. After you configure Kerberos authentication, this user is included in the <code>_infalInternalNamespace</code> security domain that the command creates.
-ServiceRealmName -srn	Kerberos_realm_name	Name of the Kerberos realm as specified in the Kerberos configuration file. The realm name must be in uppercase and is case-sensitive. The service realm name and the user realm name must be the same.

Option	Argument	Description
-UserRealmName -urn	Kerberos_realm_name	Name of the Kerberos realm as specified in the Kerberos configuration file. The service realm name and the user realm name must be the same.
-SPNShareLevel -spnSL	NODE PROCESS	Service principal level for the domain. Set to NODE to enable Kerberos at the node level. Set to PROCESS to enable Kerberos at the process level.

The following example changes the domain authentication to Kerberos and sets the nodeuser01 user account as the administrator account:

```
infasetup switchToKerberosMode -ad nodeuser01 -srn EXAMPLE.COM -urn EXAMPLE.COM -
spnSL NODE
```

Step 2. Update the Nodes in the Domain

Update all gateway and worker nodes with the Kerberos authentication server information except the gateway nodes on which you ran the `infasetup switchToKerberosMode` command.

Use the following commands to update the gateway and worker nodes:

infasetup UpdateGatewayNode

Use the `UpdateGatewayNode` command to set the Kerberos authentication parameters on a gateway node in the domain. If the domain has multiple gateway nodes, run the `UpdateGatewayNode` command on each gateway node.

infasetup UpdateWorkerNode

Use the `UpdateWorkerNode` command to set the Kerberos authentication parameters on a worker node in the domain. If the domain has multiple worker nodes, run the `UpdateWorkerNode` command on each worker node.

1. At the command prompt on a node, switch to the directory where the `infasetup` executable is located:

```
<Informatica installation directory>\isp\bin
```

2. To set the Kerberos authentication parameters on a gateway node, run the following command:

```
infasetup UpdateGatewayNode -krb <true|false> -srn <Kerberos realm name> -urn
<Kerberos realm name>
```

To set the Kerberos authentication parameters on a worker node, run the following command:

```
infasetup UpdateWorkerNode -krb <true|false> -srn <Kerberos realm name> -urn
<Kerberos realm name>
```

The following table describes the options and arguments required to enable Kerberos authentication on a node:

Option	Argument	Description
-EnableKerberos -krb	true false	Configures the Informatica domain to use Kerberos authentication. Set to true to enable Kerberos authentication. Default is false.
-ServiceRealmName -srn	Kerberos_realm_name	Name of the Kerberos realm specified in the Kerberos configuration file. The realm name must be in uppercase and is case-sensitive. The service realm name and the user realm name must be the same.
-UserRealmName -urn	Kerberos_realm_name	Name of the Kerberos realm specified in the Kerberos configuration file. The service realm name and the user realm name must be the same.

The following example updates a worker node to use Kerberos authentication:

```
infasetup updateWorkerNode -krb true -srn EXAMPLE.COM -urn EXAMPLE.COM
```

Enabling Kerberos on Informatica Nodes

After you enable Kerberos in the domain, you must copy the Kerberos configuration file to each node in the domain. You must also configure web browsers to access the Informatica web applications.

Copy the keytab files to the following directory on each node:

```
<Informatica installation directory>\isp\config\keys
```

The keytab files you copy depends on whether you enable Kerberos authentication at the node level or at the process level.

Keytab Files at Node Level

Copy each keytab file generated at the node level to the corresponding node.

The following table shows the node to which to copy each keytab file:

Keytab File	Location on Node
<node name>.keytab	Copy each file to the corresponding node.
webapp_http.keytab	Copy each file to the corresponding gateway node.
Idapuser.keytab	Copy the file to each gateway node.

Keytab Files at Process Level

Copy each keytab file generated at the process level to the corresponding node.

The following table shows the node to which to copy each keytab file:

Keytab File	Location on Node
<node name>.keytab	Copy each file to the corresponding node.
webapp_http.keytab	Copy each file to the corresponding gateway node.
_AdminConsole.keytab	Copy each file to the corresponding gateway node.
<application service name>.keytab	Copy each file to the corresponding node on which the Informatica application service runs.
Idapuser.keytab	Copy the file to each gateway node.

Configure web browsers to access Informatica web applications.

In Microsoft Internet Explorer and Google Chrome, add the URL of the Informatica web applications, such as the Analyst tool, to the list of trusted sites.

If you are using Chrome version 41 or later, you must also set the AuthServerWhitelist and AuthNegotiateDelegateWhitelist policies.

Step 1. Copy the Keytab Files to the Informatica Nodes

After you create the keytab files, copy each keytab file to the corresponding node.

Copy the keytab files to the following directory on each node:

```
<Informatica installation directory>\isp\config\keys
```

The keytab files you copy depends on whether you enable Kerberos authentication at the node level or at the process level.

Keytab Files at Node Level

Copy each keytab file generated at the node level to the corresponding node.

The following table shows the node to which to copy each keytab file:

Keytab File	Location on Node
<node name>.keytab	Copy each file to the corresponding node.
webapp_http.keytab	Copy each file to the corresponding gateway node.
Idapuser.keytab	Copy the file to each gateway node.

Keytab Files at Process Level

Copy each keytab file generated at the process level to the corresponding node.

The following table shows the node to which to copy each keytab file:

Keytab File	Location on Node
<node name>.keytab	Copy each file to the corresponding node.
webapp_http.keytab	Copy each file to the corresponding gateway node.
_AdminConsole.keytab	Copy each file to the corresponding gateway node.
<application service name>.keytab	Copy each file to the corresponding node on which the Informatica application service runs.
ldapuser.keytab	Copy the file to each gateway node.

Step 2. Enable Kerberos Authentication for Informatica Clients

Copy the Kerberos configuration file to each computer that hosts an Informatica client, and then set an environment variable to point to the configuration file. You must also enable client browsers to access the Informatica web applications.

After you configure the Informatica domain to run with Kerberos authentication, perform the following tasks on the Informatica client tools:

Copy the Kerberos configuration file to each Informatica client host.

Copy the `krb5.conf` file to each computer that hosts a Informatica client such as the PowerCenter Client or Informatica Developer (the Developer tool). Copy the file to the following directory on each host:

```
<Informatica installation directory>\clients\shared\security
```

Set the KRB5_CONFIG environment variable on each Informatica client host.

Set the KRB5_CONFIG environment variable to the path and file name of the Kerberos configuration file on each computer that hosts Informatica clients such as the PowerCenter Client and the Developer tool.

Configure web browsers to access Informatica web applications.

In Microsoft Internet Explorer and Google Chrome, add the URL of the Informatica web applications, such as the Analyst tool, to the list of trusted sites.

If you are using Chrome version 41 or later, you must also set the `AuthServerWhitelist` and `AuthNegotiateDelegateWhitelist` policies.

Enabling User Accounts to Use Kerberos Authentication

After you enable Kerberos authentication in the domain, import Informatica user accounts from Active Directory into the LDAP security domain that contains Kerberos user accounts. You must also migrate the groups, roles, privileges, and permissions from the native security domain to the corresponding Active Directory user accounts in the LDAP security domain that contains Kerberos user accounts.

Step 1. Import User Accounts from Active Directory into an LDAP Security Domain

Import Informatica user accounts from Active Directory into the LDAP security domain that contains Kerberos user accounts.

When you enable Kerberos authentication in the domain, Informatica creates an empty LDAP security domain with the same name as the Kerberos realm. You can import user accounts from Active Directory into this LDAP security domain, or you can import the user accounts into a different LDAP security domain.


You use the Administrator tool to import the user accounts that use Kerberos authentication from Active Directory into an LDAP security domain.

1. Start the domain and all Informatica services. Start the services in the following order:
 - Model Repository Service
 - Data Integration Service
 - Analyst Service
 - Content Management Service
 - PowerCenter® Repository Service
 - PowerCenter® Integration Service
 - Metadata Manager Service
2. Log in to Windows with the administrator account you specified when you enabled Kerberos authentication in the domain.

The following image shows the user name and password for nodeuser01 entered in the login dialog box:



3. Log in to the Administrator tool. Select _infaInternalNamespace as the security domain.
The following image shows _infaInternalNamespace selected as the security domain:



4. In the Administrator tool, click the **Security** tab.
5. Click the **Actions** menu and select **LDAP Configuration**.
6. In the **LDAP Configuration** dialog box, click the **LDAP Connectivity** tab.
7. Configure the connection properties for the Active Directory.

You might need to consult the LDAP administrator to get the information needed to connect to the LDAP server.

The following table describes the LDAP server configuration properties:

Property	Description
Server name	Host name or IP address of the Active Directory server.
Port	Listening port for the Active Directory server.
LDAP Directory Service	Select Microsoft Active Directory Service.
Name	Specify the bind user account you created in Active Directory to synchronize accounts in Active Directory with the LDAP security domain. Because the domain is enabled for Kerberos authentication, you do not have the option to provide a password for the account.
Use SSL Certificate	Indicates that the LDAP server uses the Secure Socket Layer (SSL) protocol.
Trust LDAP Certificate	Determines whether the Service Manager can trust the SSL certificate of the LDAP server. If selected, the Service Manager connects to the LDAP server without verifying the SSL certificate. If not selected, the Service Manager verifies that the SSL certificate is signed by a certificate authority before connecting to the LDAP server.

Property	Description
Not Case Sensitive	Indicates that the Service Manager must ignore case sensitivity for distinguished name attributes when assigning users to groups.
Group Membership Attribute	Name of the attribute that contains group membership information for a user. This is the attribute in the LDAP group object that contains the DN's of the users or groups who are members of a group. For example, <i>member</i> or <i>memberof</i> .
Maximum Size	Maximum number of user accounts to import into a security domain. For example, if the value is set to 100, you can import a maximum of 100 user accounts into the security domain. If the number of user to be imported exceeds the value for this property, the Service Manager generates an error message and does not import any user. Set this property to a higher value if you have many users to import. Default is 1000.

The following image shows the `ldapuser` user account specified with the connection details for an Active Directory server set in the LDAP Connectivity panel of the **LDAP Configuration** dialog box:

LDAP Configuration

Fields marked with an asterisk (*) are required.

LDAP Connectivity | Security Domains | Schedule

This domain is running under kerberos authentication mode

Server name and port for the LDAP server

Server Name *

Port *

LDAP Directory Service *

Name

SSL certificate for the LDAP server

☐ Use SSL Certificate

☐ Trust LDAP Certificate

☐ Not Case Sensitive

Group attribute definition

Group Membership Attribute

Maximum number of users to import for a security domain

Maximum size *

- In the **LDAP Configuration** dialog box, click the **Security Domains** tab.
- Click **Add**.

The following table describes the filter properties that you can set for a security domain:

Property	Description
Security Domain	Name of the LDAP security domain into which you want to import user accounts from Active Directory.
User search base	Distinguished name (DN) of the entry that serves as the starting point to search for user names in Active Directory. The search finds an object in the directory according to the path in the distinguished name of the object. For example, to search the USERS container that contains Informatica user accounts in the example.com Windows domain, specify CN=USERS,DC=EXAMPLE,DC=COM.
User filter	An LDAP query string that specifies the criteria for searching for users in the directory service. The filter can specify attribute types, assertion values, and matching criteria. For example: <code>(objectclass=*)</code> searches all objects. <code>(&(objectClass=user)(!(cn=susan)))</code> searches all user objects except "susan". For more information about search filters, see the documentation for the LDAP directory service.
Group search base	Distinguished name (DN) of the entry that serves as the starting point to search for group names in the LDAP directory service.
Group filter	An LDAP query string that specifies the criteria for searching for groups in the directory service.

The following image shows the information required to import LDAP users from Active Directory into the LDAP security domain created when you enabled Kerberos in the domain:

The screenshot shows the 'LDAP Configuration' dialog box with the 'Security Domains' tab selected. The dialog has three tabs: 'LDAP Connectivity', 'Security Domains', and 'Schedule'. Below the tabs, there is a message: 'Fields marked with an asterisk (*) are required.' and 'You can specify multiple security domains for LDAP users and groups. Click Add to add a new security domain.' There is a green plus icon and the word 'Add'. Below this is a section titled 'Add new Security Domain' with a dropdown arrow, a magnifying glass icon, and the words 'Preview' and 'Cancel'. The form contains five fields: 'Security Domain *' with the value 'COMPANY.COM', 'User search base' with the value 'CN=USERS,DC=COMPANY,DC=COM', 'User filter' (empty), 'Group search base' (empty), and 'Group filter' (empty). At the bottom of the dialog are three buttons: 'Synchronize Now', 'OK', and 'Cancel'.

10. Click **Synchronize Now**.

The Service Manager synchronizes the users in all the LDAP security domains with the users in the LDAP directory service. The time it takes for the synchronization process to complete depends on the number of users and groups to be imported.

11. Click **OK** to save the LDAP security domain.

Step 2. Migrate Native User Privileges and Permissions to the Kerberos Security Domain

If the Informatica domain has user accounts in the native security domain, the corresponding Active Directory user accounts in the Kerberos security domain must have the same groups, roles, privileges, and permissions. Migrate the groups, roles, privileges, and permissions of the native users to the corresponding user accounts in the Kerberos LDAP security domain.

1. Review the list of native user accounts and determine the accounts that you want to migrate to the LDAP security domain for Kerberos authentication.

To list the user accounts in the Informatica domain, run the following command:

```
infacmd isp ListAllUsers
```

Each native user account that you want to migrate to the Kerberos security domain must have a corresponding account in the Active Directory service that you use for Kerberos authentication.

2. Create the user migration file.

The user migration file is a plain text file that contains the list of native users and the corresponding Kerberos users that require the same groups, roles, privileges, and permissions.

Use the following format to list entries in the user migration file:

```
Native/<source user name>,<LDAP security domain>/<target user name>
```

The following example shows a user migration file containing the following list of users to migrate to the COMPANY.COM security domain:

```
Native/User1,COMPANY.COM/User1
Native/User2,COMPANY.COM/User2
Native/User3,COMPANY.COM/User3
```

3. Run the infacmd isp migrateUsers command to migrate account privileges and permissions in the native security domain to the accounts in the Kerberos security domain.

To migrate the groups, roles, privileges, and permissions for users, run the following command:

```
infacmd isp migrateUsers -dn <domain name> -un <administrator user name> -pd
<administrator password> -sdn <security domain> -umf <user migration file>
```

The following table describes the options for the command:

Option	Description
-DomainName -dn	Name of the Informatica domain.
-UserName -un	User name to connect to the domain. Specify the user name of the administrator account you specified in the infasetup switchToKerberosMode command.
-Password -pd	Password for the administrator account.
-SecurityDomain -sdn	LDAP security domain of the administrator account used to connect to the domain. Specify _infaInternalNamespace.
-UserMigrationFile -umf	Path and file name of the user migration file. The command skips entries with a duplicate source user name or target user name.

The following example migrates the groups, roles, privileges, and permissions for users based on the um_s.txt user migration file:

```
infacmd isp migrateUsers -dn InfaDomain -un nodeuser01 -pd password -sdn
_infaInternalNamespace -umf C:\Infa\um_s.txt
```

The command overwrites the connection object permissions assigned to the LDAP user with the connection object permissions for the native user. The command merges the groups, roles, privileges, and domain object permissions for native users and corresponding LDAP users.

The migrateUsers command creates a detailed log file named infacmd_uml_<date>_<time>.txt in the directory where you run the command.

CHAPTER 5

Domain Security

This chapter includes the following topics:

- [Domain Security Overview, 57](#)
- [Secure Communication Within the Domain, 58](#)
- [Secure Connections to a Web Application Service, 68](#)
- [Cipher Suites for the Informatica Domain, 71](#)
- [Secure Sources and Targets, 73](#)
- [Secure Data Storage, 75](#)
- [Application Services and Ports, 79](#)

Domain Security Overview

You can enable options in the Informatica domain to configure secure communication between the components in the domain and between the domain and client components.

You can enable different options to secure specific components in the domain. You do not have to secure all components in the domain. For example, you can secure the communication between the services in the domain but not secure the connection between the Model Repository Service and the repository database.

Informatica uses the TCP/IP and HTTP protocols to communicate between components in the domain. The domain uses SSL certificates to secure communication between components.

When you install the Informatica services, you can enable secure communication for the services in the domain and for the Administrator tool. After installation, you can configure secure communication in the domain in the Administrator tool or from the command line.

During installation, the installer generates an encryption key to encrypt sensitive data, such as passwords, that are stored in the domain. You can provide the keyword that the installer uses to generate the encryption key. After installation, you can change the encryption key for sensitive data. You must upgrade the content of repositories to update the encrypted data.

You can enable secure communication in the following areas:

Domain

Within the domain, you can select options to enable secure communication for the following components:

- Between the Service Manager, the services in the domain, and the Informatica client tools
- Between the domain and the domain configuration repository

- Between the repository services and repository databases
- Between the PowerCenter Integration Service and DTM processes

Web application services

You can secure the connection between a web application service, such as the Analyst Service, and the browser

Sources and targets

You can enable secure communication between the Data Integration Service and PowerCenter Integration Service and the source and target databases.

Data storage

Informatica encrypts sensitive data, such as passwords, when it stores data in the domain. Informatica generates an encryption key based on a keyword that you provide during installation. Informatica uses the encryption key to encrypt and decrypt sensitive data that are stored in the domain.

Secure Communication Within the Domain

You can use the Secure Communication option to secure the connection between services and between services and the service managers in the domain. Additionally, you can enable security for workflows and use secure databases for the repositories that you create in the domain.

After you secure the domain, configure the Informatica client applications to work with a secure domain.

Secure Communication for Services and the Service Manager

You can configure secure communication within the domain during installation. After installation, you can configure secure communication for the domain on the Administrator tool or from the command line.

Informatica provides an SSL certificate that you can use to secure the domain. However, you should provide a custom SSL certificate for domains that require a higher level of security, such as a domain in a production environment. Specify the keystore and truststore files that contain the SSL certificates you want to use.

Note: Informatica provides SSL certificates for evaluation purposes. If you do not provide an SSL certificate, Informatica uses the same default private key for all Informatica installations. The security of your domain could be compromised. Provide an SSL certificate to ensure a high level of security for the domain. The certificate that you provide can be self-signed or from a certificate authority (CA).

When you configure secure communication for the domain, you secure the connections between the following components:

- The Service Manager and all services running in the domain
- The Data Integration Service and the Model Repository Service
- The Data Integration Service and the workflow processes
- The PowerCenter Integration Service and the PowerCenter Repository Service
- The domain services and the Informatica client tools and command line programs

Requirements for Secure Communication within the Domain

Before you enable secure communication within the domain, ensure that the following requirements are met:

You created a certificate signing request (CSR) and private key.

You can use keytool or OpenSSL to create the CSR and private key.

If you use RSA encryption, you must use more than 512 bits.

You have a signed SSL certificate.

The certificate can be self-signed or CA signed. Informatica recommends a CA signed certificate.

You imported the certificate into keystores.

You must have a keystore in PEM format named `infa_keystore.pem` and a keystore in JKS format named `infa_keystore.jks`.

Note: The password for the keystore in JKS format must be the same as the private key pass phrase used to generate the SSL certificate.

You imported the certificate into truststores.

You must have a truststore in PEM format named `infa_keystore.pem` and a keystore in JKS format named `infa_keystore.jks`.

The keystores and truststores are in the correct directory.

If you enable secure communication during installation, the keystore and truststore must be in a directory that is accessible to the installer.

If you enable secure communication after installation, the keystore and truststore must be in a directory that is accessible to the command line programs.

For more information about how to create a custom keystore and truststore, see the Informatica How-To Library article [How to Create Keystore and Truststore Files for Secure Communication in the Informatica Domain](https://kb.informatica.com/h2l/HowTo%20Library/1/0700-CreateKeystoresAndTruststores-H2L.pdf): <https://kb.informatica.com/h2l/HowTo%20Library/1/0700-CreateKeystoresAndTruststores-H2L.pdf>

After you secure the domain, configure the Informatica client applications to work with a secure domain.

Enabling Secure Communication for the Domain from the Command Line

Use the `infacmd` and `infasetup` commands to enable secure communication for the domain. After you enable secure communication, you must restart the domain for the change to take effect.

To use your SSL certificate files, specify the keystore and truststore files when you run the `infasetup` command.

To configure secure domain communication from the command line, use the following commands:

infacmd isp UpdateDomainOptions

Use the `UpdateDomainOptions` command to set the secure communication mode for the domain.

infasetup UpdateGatewayNode

Use the `UpdateGatewayNode` command to enable secure communication for the Service Manager on a gateway node in a domain. If the domain has multiple gateway nodes, run the `UpdateGatewayNode` command on each gateway node.

infasetup UpdateWorkerNode

Use the `UpdateWorkerNode` command to enable secure communication for the Service Manager on a worker node in a domain. If the domain has multiple worker nodes, run the `UpdateWorkerNode` command on each worker node.

1. Verify that the domain you want to secure is running.
2. Update the domain.

Run the following command with the required options and arguments:

- Windows: `infacmd isp UpdateDomainOptions`
- UNIX: `infacmd.sh isp UpdateDomainOptions`

To configure secure communication for the domain, include the following option when you run the `infacmd` command:

Option	Argument	Description
-DomainOptions -do	option_name=value	Set the following option to configure secure communication for the domain: TLSMode=True

3. Shut down the domain.

The domain must be shut down before you run the `infasetup` commands.

4. Run `infasetup` with the required options and arguments.

Enter the following command:

- Windows: `infasetup UpdateGatewayNode` **or** `infasetup UpdateWorkerNode`
- UNIX: `infasetup.sh UpdateGatewayNode` **or** `infasetup.sh UpdateWorkerNode`

To configure secure communication on the nodes, run the commands with the following options:

Option	Argument	Description
-EnableTLS -tls	enable_tls	Configures secure communication for the services in the Informatica domain.
-NodeKeystore -nk	node_keystore_directory	Optional if you use the default SSL certificate from Informatica. Required if you use your SSL certificate. Directory that contains the keystore files. The Informatica domain requires the SSL certificate in PEM format and in Java Keystore (JKS) files. The directory must contain keystore files in PEM and JKS formats. The keystore files must be named <code>infa_keystore.jks</code> and <code>infa_keystore.pem</code> . You can use the same keystore file for multiple nodes.
-NodeKeystorePass -nkp	node_keystore_password	Optional if you use the default SSL certificate from Informatica. Required if you use your SSL certificate. Password for the <code>infa_keystore.jks</code> file.

Option	Argument	Description
-NodeTruststore -nt	node_truststore_directory	Optional if you use the default SSL certificate from Informatica. Required if you use your SSL certificate. Directory that contains the truststore files. The Informatica domain requires the SSL certificate in PEM format and in Java Keystore (JKS) files. The directory must contain truststore files in PEM and JKS formats. The truststore files must be named infa_truststore.jks and infa_truststore.pem. You can use the same truststore file for multiple nodes.
-NodeTruststorePass -ntp	node_truststore_password	Optional if you use the default SSL certificate from Informatica. Required if you use your SSL certificate. Password for the infa_truststore.jks file.

5. Run the infasetup command on each node in the domain.

If you have multiple gateway nodes in the domain, run infasetup UpdateGatewayNode on each gateway node. If you have multiple worker nodes, run infasetup UpdateWorkerNode on each worker node. You must use the same keystore and truststore files for all nodes in the domain.

6. Restart the domain.

After you complete updating all nodes in the domain, you must update the machines that host the Informatica client tools. Set the location of the SSL certificates in the Informatica truststore environment variables.

Enabling Secure Communication for the Domain in the Administrator Tool

You can use the Administrator tool to enable secure communication for the domain. When you enable secure communication in the Administrator tool, you must also run infasetup commands to update the nodes.

When you enable the Secure Communication option in the Administrator tool, you also need to run the infasetup command to update Informatica configuration files on each node. To specify the SSL certificate files to use, specify the keystore and truststore files when you run the infasetup command.

To update the Informatica configuration files on each node, use the following commands:

infasetup UpdateGatewayNode

Use the UpdateGatewayNode command to enable secure communication for the Service Manager on a gateway node in a domain. If the domain has multiple gateway nodes, run the UpdateGatewayNode command on each gateway node.

infasetup UpdateWorkerNode

Use the UpdateWorkerNode command to enable secure communication for the Service Manager on a worker node in a domain. If the domain has multiple worker nodes, run the UpdateWorkerNode command on each worker node.

To enable secure domain communication from the Administrator tool, perform the following steps:

1. On the Administrator tool, select the domain.
2. In the contents panel, click the **Properties** view.
3. Go to the **General Properties** section and click **Edit**.
4. On the **Edit General Properties** window, select **Enable Secure Communication**.
5. Click **OK**

6. Shut down the domain.

The domain must be shut down before you run the infasetup commands.

7. Run infasetup with the required options and arguments.

Enter the following command:

- Windows: `infasetup UpdateGatewayNode` or `infasetup UpdateWorkerNode`
- UNIX: `infasetup.sh UpdateGatewayNode` or `infasetup.sh UpdateWorkerNode`

To configure secure communication on the nodes, run the commands with the following options:

Option	Argument	Description
-EnableTLS -tls	enable_tls	Configures secure communication for the services in the Informatica domain.
-NodeKeystore -nk	node_keystore_directory	Optional if you use the default SSL certificate from Informatica. Required if you use your SSL certificate. Directory that contains the keystore files. The Informatica domain requires the SSL certificate in PEM format and in Java Keystore (JKS) files. The directory must contain keystore files in PEM and JKS formats. The keystore files must be named <code>infa_keystore.jks</code> and <code>infa_keystore.pem</code> . You can use the same keystore file for multiple nodes.
-NodeKeystorePass -nkp	node_keystore_password	Optional if you use the default SSL certificate from Informatica. Required if you use your SSL certificate. Password for the <code>infa_keystore.jks</code> file.
-NodeTruststore -nt	node_truststore_directory	Optional if you use the default SSL certificate from Informatica. Required if you use your SSL certificate. Directory that contains the truststore files. The Informatica domain requires the SSL certificate in PEM format and in Java Keystore (JKS) files. The directory must contain truststore files in PEM and JKS formats. The truststore files must be named <code>infa_truststore.jks</code> and <code>infa_truststore.pem</code> . You can use the same truststore file for multiple nodes.
-NodeTruststorePass -ntp	node_truststore_password	Optional if you use the default SSL certificate from Informatica. Required if you use your SSL certificate. Password for the <code>infa_truststore.jks</code> file.

8. Run the infasetup command on each node in the domain.

If you have multiple gateway nodes in the domain, run `infasetup UpdateGatewayNode` on each gateway node. If you have multiple worker nodes, run `infasetup UpdateWorkerNode` on each worker node. You must use the same keystore and truststore files for all nodes in the domain.

9. Restart the domain.

After you complete updating all nodes in the domain, you must update the machines that host the Informatica client tools. Set the location of the SSL certificates in the Informatica truststore environment variables.

Configuring the Informatica Client Applications to Work with a Secure Domain

When you enable secure communication within the domain, you also secure connections between the domain and Informatica client applications, such as the Developer tool. You might need to specify the location and password for the truststore files that you use to secure the domain in environment variables. You set the environment variables on machines hosting client applications that access services within the domain.

SSL certificates that are used to secure an Informatica domain are contained in truststore files named `infa_truststore.jks` and `infa_truststore.pem`. The truststore files must be available on each client host.

You might need to set the following environment variables on each client host:

INFA_TRUSTSTORE

Set this variable to the directory that contains the `infa_truststore.jks` and `infa_truststore.pem` truststore files.

INFA_TRUSTSTORE_PASSWORD

Set this variable to the password for the truststore. The password must be encrypted. Use the command line program `mpasswd` to encrypt the password.

Informatica provides an SSL certificate in default truststore files that you can use to secure the domain. When you install the Informatica clients, the installer sets the environment variables and installs the truststore files in the following directory by default: `<Informatica installation directory>\clients\shared\security`

If you use the default Informatica SSL certificate, and the `infa_truststore.jks` and `infa_truststore.pem` files are in the default directory, you do not need to set the `INFA_TRUSTSTORE` or `INFA_TRUSTSTORE_PASSWORD` environment variables.

You must set the `INFA_TRUSTSTORE` and `INFA_TRUSTSTORE_PASSWORD` environment variables on each client host in the following scenarios:

You use a custom SSL certificate to secure the domain.

If you provide an SSL certificate to use to secure the domain, import the certificate into truststore files named `infa_truststore.jks` and `infa_truststore.pem`, and then copy the truststore files to each client host. You must specify the location of the files and the truststore password.

You replace the default Informatica truststore files with your own truststore files in the default directory.

If you replace the default the `infa_truststore.jks` and `infa_truststore.pem` truststore files with your own truststore files in the default Informatica directory, you must specify the truststore password. The truststore files must have the same filenames as the default truststore files.

You use the default Informatica SSL certificate, but the truststore files are not in the default Informatica directory.

If you use the default Informatica SSL certificate, but the default `infa_truststore.jks` and `infa_truststore.pem` truststore files are not in the default directory, you must specify the location of the files and the truststore password.

Secure Domain Configuration Repository Database

The Informatica domain configuration repository stores configuration information and user account privileges and permissions. When you create an Informatica domain, you must create a domain configuration repository.

You can create a domain configuration repository on a database that is secured with the SSL protocol. The SSL protocol uses SSL certificates stored in a truststore file. Access to the secure database access requires a truststore that contains the certificates for the database.

You can create a secure domain configuration repository database when you install the Informatica services and create a domain. For more information about configuring a secure domain configuration repository during installation, see the Informatica installation guides.

After installation, you can configure a secure domain configuration repository database from the command line.

Note: Before you configure a secure domain configuration repository database after installation, you must enable secure communication for the domain.

You can create a secure domain configuration repository on the following databases:

- Oracle
- Microsoft SQL Server
- IBM DB2

Configuring a Secure Domain Configuration Repository Database

After installation, you can change the domain configuration repository to a secure database. You can use a secure domain configuration repository database only if you enable secure communication for the domain.

You must shut down the domain before you change the domain configuration repository database. Use the `infasetup` command to back up the domain configuration repository database and to restore it in a secure database. When you restore the domain configuration repository in the secure database, specify the security parameters for the secure database. Then update the gateway node with the domain configuration repository information.

To back up and restore the repository database and update the gateway node, use the following commands:

infasetup BackupDomain

Use the `BackupDomain` option to back up data from the domain configuration repository database.

infasetup RestoreDomain

Use the `RestoreDomain` option to restore domain configuration repository data to a secure database.

infasetup UpdateGatewayNode

Use the `UpdateGatewayNode` option update the domain configuration repository settings in the gateway nodes of the domain.

To change the domain configuration repository to a secure database, complete the following steps:

1. Verify that secure communication is enabled for the domain.
The domain must be secure before you can use a secure database for the domain configuration repository.

2. Shut down the domain.

3. Run the `infasetup BackupDomain` command and specify the database connection information.

When you run the `BackupDomain` command, `infasetup` backs up most of the domain configuration database tables to the file name you specify.

Note: If the `infasetup` backup or restore command fails with a Java memory error, increase the system memory available for `infasetup`. To increase system memory, set the `-Xmx` value in the `INFA_JAVA_CMD_OPTS` environment variable.

4. Use the database backup utility to manually back up additional repository tables that the `infasetup` command does not back up.

Back up the contents of the following table:

- ISP_RUN_LOG

5. To restore the domain configuration repository in the secure database, run the `infasetup RestoreDomain` command and specify the database connection information.

In addition to the connection information, specify the following options required for the secure database:

Option	Argument	Description
-DatabaseTlsEnabled -dbtls	database_tls_enabled	Required. Indicates whether the database into which the domain configuration repository will be restored is a secure database. Set this option to True.
-DatabaseTruststoreLocation -dbtl	database_truststore_location	Required. Path and file name of the truststore file that contains the SSL certificate for the database.
-DatabaseTruststorePassword -dbtp	database_truststore_password	Required. Password for the database truststore file for the secure database.

In the connection string, include the following security parameters:

EncryptionMethod

Required. Indicates whether data is encrypted when transmitted over the network. This parameter must be set to `SSL`.

ValidateServerCertificate

Optional. Indicates whether Informatica validates the certificate that the database server sends.

If this parameter is set to `True`, Informatica validates the certificate that the database server sends. If you specify the `HostNameInCertificate` parameter, Informatica also validates the host name in the certificate.

If this parameter is set to `False`, Informatica does not validate the certificate that the database server sends. Informatica ignores any truststore information that you specify.

Default is `True`.

HostNameInCertificate

Optional. Host name of the machine that hosts the secure database. If you specify a host name, Informatica validates the host name included in the connection string against the host name in the SSL certificate.

cryptoProtocolVersion

Required. Specifies the cryptographic protocol to use to connect to a secure database. You can set the parameter to `cryptoProtocolVersion=TLSv1.1` or `cryptoProtocolVersion=TLSv1.2` based on the cryptographic protocol used by the database server.

6. Use the database restore utility to restore the repository tables that you manually backed up.

Restore the following table:

- ISP_RUN_LOG

7. To update the nodes in the domain with information about the secure domain configuration repository, run the `infasetup UpdateGatewayNode` command and specify the secure database connection information.

In addition to the node options, specify the following options required for the secure database:

Option	Argument	Description
-DatabaseTlsEnabled -dbtls	database_tls_enabled	Required. Indicates the database used for the domain configuration repository is a secure database. Set this option to True.
-DatabaseConnectionString -cs	database_connection_string	Required. Connection string to use to connect to the secure database. The connection string must include the security parameters that you included in the connection string when you ran the infasetup RestoreDomain command in step 5
-DatabaseTruststorePassword -dbtp	database_truststore_password	Required. Password for the database truststore file for the secure database.

If you have multiple gateway nodes in the domain, run infasetup UpdateGatewayNode on each gateway node.

8. Restart the domain.

Secure PowerCenter Repository Database

When you create a PowerCenter Repository Service, you can create the associated PowerCenter repository on a database secured with the SSL protocol.

The PowerCenter Repository Service connects to the PowerCenter repository database through native connectivity.

When you create a PowerCenter repository on a secure database, verify that the database client files contain the secure connection information for the database. For example, if you create a PowerCenter repository on a secure Oracle database, configure the Oracle database tnsnames.ora and sqlnet.ora client files with the secure connection information.

Secure Model Repository Database

When you create a Model Repository Service, you can create the associated Model repository in a database secured with the SSL protocol.

The Model Repository Service connects to the Model repository database through JDBC drivers.

1. Set up a database secured with the SSL protocol.
2. In the Administrator tool, create a Model Repository Service.
3. In the **New Model Repository Service** dialog box, enter the general properties for the Model Repository Service and click **Next**.
4. Enter the database properties and the JDBC connection string for the Model Repository Service.

To connect to a secure database, enter the secure database parameters in the **Secure JDBC Parameters** field. Informatica treats the value of **Secure JDBC Parameters** field as sensitive data and stores the parameter string encrypted.

The following list describes the secure database parameters:

EncryptionMethod

Required. Indicates whether data is encrypted when transmitted over the network. This parameter must be set to `SSL`.

ValidateServerCertificate

Optional. Indicates whether Informatica validates the certificate that the database server sends.

If this parameter is set to `True`, Informatica validates the certificate that the database server sends. If you specify the `HostNameInCertificate` parameter, Informatica also validates the host name in the certificate.

If this parameter is set to `False`, Informatica does not validate the certificate that the database server sends. Informatica ignores any truststore information that you specify.

Default is `True`.

HostNameInCertificate

Optional. Host name of the machine that hosts the secure database. If you specify a host name, Informatica validates the host name included in the connection string against the host name in the SSL certificate.

cryptoProtocolVersion

Required. Specifies the cryptographic protocol to use to connect to a secure database. You can set the parameter to `cryptoProtocolVersion=TLSv1.1` or `cryptoProtocolVersion=TLSv1.2` based on the cryptographic protocol used by the database server.

TrustStore

Required. Path and file name of the truststore file that contains the SSL certificate for the database. If you do not include the path for the truststore file, Informatica looks for the file in the following default directory: `<InformaticaInstallationDirectory>/tomcat/bin`

TrustStorePassword

Required. Password for the truststore file for the secure database.

Note: Informatica appends the secure JDBC parameters to the JDBC connection string. If you include the secure JDBC parameters directly to the connection string, do not enter any parameter in the **Secure JDBC Parameters** field.

5. Test the connection to verify that the connection to the secure repository database is valid.
6. Complete the process to create a Model Repository Service.

Secure Communication for Workflows and Sessions

By default, when you enable secure communication option for the domain, Informatica secures the connection between the Data Integration Service and PowerCenter Integration Service and the DTM processes.

In addition, if you run PowerCenter sessions on a grid, you can enable an option to secure the data communication between the DTM processes.

To enable secure data communication between DTM processes in PowerCenter sessions, select the **Enable Data Encryption** option for the PowerCenter Integration Service.

Note: PowerCenter sessions require more CPU and memory when the DTM processes run in secure mode. Before you enable secure data communication between DTM processes for PowerCenter sessions, determine whether the domain resources are adequate for the additional load.

Enabling Secure Communication for PowerCenter DTM Processes

To secure the connection between the DTM processes in PowerCenter sessions running on a grid, configure the PowerCenter Integration Service to enable the data encryption for DTM processes.

1. In the Navigator of the Administrator tool, select the PowerCenter Integration Service.
2. In the contents panel, click the Properties view.
3. Go to the PowerCenter Integration Service Properties section and click Edit.
4. On the **Edit PowerCenter Integration Service Properties** window, select **Enable Data Encryption**.
5. Click **OK**.

When you run a PowerCenter session on a grid, the DTM processes send encrypted data when they communicate with other DTM processes.

Secure Connections to a Web Application Service

To protect data that is transmitted between a web application service and the browser, secure the connection between the web application service and the browser.

You can secure the following connections:

Connections to the Administrator tool

You can secure the connection between the Administrator tool and the browser.

Connections to web application services

You can secure the connection between the following web application services and the browser:

- Analyst Service
- Metadata Manager Service
- Test Data Manager Service
- Web Services Hub Console Service

Requirements for Secure Connections to Web Application Services

Before you secure the connection to a web application service, ensure that the following requirements are met:

You created a certificate signing request (CSR) and private key.

You can use keytool or OpenSSL to create the CSR and private key.

If you use RSA encryption, you must use more than 512 bits.

You have a signed SSL certificate.

The certificate can be self-signed or CA signed. Informatica recommends a CA signed certificate.

You imported the certificate into a keystore in JKS format.

A keystore must contain only one certificate. If you use a unique certificate for each web application service, create a separate keystore for each certificate. Alternatively, you can use a shared certificate and keystore.

If you use the installer-generated SSL certificate for the Administrator tool, you do not need to import the certificate into a keystore in JKS format.

The keystore is in an accessible directory.

The keystore must be in a directory that is accessible to the Administrator tool and the command line programs.

Enabling Secure Connections to the Administrator Tool

After installation, you can configure secure connections to the Administrator tool from the command line.

You must update the gateway nodes in the domain with the properties for a secure connection between the browser and the Informatica Administrator service.

To update the gateway node with secure connection properties, run the following command: `infasetup UpdateGatewayNode`

Include the following options:

Option	Argument	Description
-HttpsPort -hs	AdminConsole_https_port	Port number to use for a secure connection to the Informatica Administrator service.
-KeystoreFile -kf	AdminConsole_Keystore_File	Path and file name of the keystore file to use for the HTTPS connection to the Informatica Administrator service.
-KeystorePass -kp	AdminConsole_Keystore_Password	Password for the keystore file.

If you have multiple gateway nodes in the domain, run the command on each gateway node.

Informatica Web Application Services

Configure a secure connection for a web application service when you create or configure it. Each application service has specific properties for the secure HTTPS connection.

Security for the Analyst Tool

When you create the Analyst Service, you can configure the secure HTTPS properties for the Analyst tool.

To secure the connection between the browser and the Analyst Service, configure the following Analyst Service properties:

Property	Description
Enable Secure Communication	Select to enable a secure connection between the Analyst tool and the Analyst Service.
HTTPS Port	Port number that the Informatica Analyst web application runs on when you enable the Transport Layer Security (TLS) protocol. Use a different port number than the HTTP port number.
Keystore File	Directory where the keystore file that contains the digital certificates is stored.

Property	Description
Keystore Password	Plain-text password for the keystore file. If this property is not set, the Analyst Service uses the default password <i>changeit</i> .
SSL Protocol	Informatica recommends that you leave this field blank. The version of TLS enabled depends on the value. A blank field enables the highest version of TLS available. If you enter a value, earlier versions of TLS might be enabled. The behavior is based on the Java version for your environment. For more information, see the documentation for your Java version.

Security for the Web Services Hub Console

When you create the Web Services Hub Service, you can configure the secure HTTPS properties for the Web Services Hub console.

To secure the connection between the browser and the Web Services Hub Service, configure the following Web Services Hub Service properties:

Property	Description
URLScheme	Indicates the security protocol that you configure for the Web Services Hub: <ul style="list-style-type: none"> - HTTP. Run the Web Services Hub on HTTP only. - HTTPS. Run the Web Services Hub on HTTPS only. - HTTP and HTTPS. Run the Web Services Hub in HTTP and HTTPS modes.
HubPortNumber (https)	Port number for the Web Services Hub on HTTPS. Appears when the URL scheme selected includes HTTPS. Required if you choose to run the Web Services Hub on HTTPS. Default is 7343.
Keystore File	Path and file name of the keystore file that contains the keys and certificates that are required for an HTTPS connection.
Keystore Password	Password for the keystore file. If this property is not set, the Web Services Hub uses the default password <i>changeit</i> .

Security for Metadata Manager

When you create the Metadata Manager Service, you can configure the secure HTTPS properties for the Metadata Manager web application.

To secure the connection between the browser and the Metadata Manager Service, configure the following Metadata Manager Service properties:

Property	Description
Enable Secure Sockets Layer	Indicates that you want to configure a secure connection for the Metadata Manager web application. Note: This property is displayed when you create a Metadata Manager Service. To secure the connection for an existing Metadata Manager Service, set the URL Scheme configuration property to HTTPS.
Port Number	Port number that the Metadata Manager application runs on. Default is 10250.

Property	Description
Keystore File	Keystore file that contains the keys and certificates required if you configure a secure connection for the Metadata Manager web application. Note: The Metadata Manager Service uses RSA encryption. Therefore, Informatica recommends that you use a security certificate that was generated with the RSA algorithm.
Keystore Password	Password for the keystore file.

Cipher Suites for the Informatica Domain

You can configure the cipher suites that the Informatica domain uses when it encrypts connections within the Informatica domain. Connections from the Informatica domain to resources outside of the domain are not affected by the cipher suite configuration.

When you enable secure communication for the Informatica domain or secure connections to web application services, the Informatica domain uses cipher suites to encrypt traffic.

Informatica creates the effective list of cipher suites that it uses based on the following lists:

Blacklist

List of cipher suites that you want the Informatica domain to block. When you blacklist a cipher suite, the Informatica domain removes the cipher suite from the effective list. You can add cipher suites that are on the default list to the blacklist.

Default list

List of cipher suites that Informatica domain supports by default. If you do not configure a whitelist or blacklist, the Informatica domain uses the default list as the effective list.

For more information, see [Appendix C, "Default List of Cipher Suites" on page 247](#)

Whitelist

List of cipher suites that you want the Informatica domain to support. When you add a cipher suite to the whitelist, the Informatica domain adds the cipher suite to the effective list. You do not need to add cipher suites that are on the default list to the whitelist.

Informatica creates the effective list by adding cipher suites from the whitelist to the default list and removing cipher suites on the blacklist from the default list.

Consider the following guidelines for effective lists:

- To use a custom effective list for secure connections to web clients, the Informatica domain must use secure communication within the domain. If the domain does not use secure communication, Informatica uses the default list as the effective list.
- The effective list only governs connections within the Informatica domain. Connections to data sources do not use the effective list.
- The effective list must contain at least one cipher suite that TLS v1.1 or 1.2 supports.
- The effective list must be a valid cipher suite for Windows, the Java Runtime Environment, and OpenSSL.

Configure the Informatica Domain to Use Advanced Ciphers

If you want to use advanced cipher suites that use AES-256 to provide a higher level of security, you must replace the Java Cryptography Extension (JCE) policy files installed with the Java Runtime Environment (JRE) on each node in the domain with the unlimited strength JCE policy files. The unlimited strength JCE policy files contain no restrictions on cryptographic strengths.

1. Download the Java Cryptography Extension (JCE) Unlimited Strength Jurisdiction Policy Files 8 archive.
2. Shut down the domain.
3. Go to the following directory on the domain node:
`<Informatica installation directory>\java\jre\lib\security\`
4. Replace the following JAR files with the JAR files extracted from the archive:
 - local_policy.jar
 - US_export_policy.jar
5. Restart the domain.

Create the Cipher Suite Lists

To configure the Informatica domain to use specific cipher suites, create a whitelist specifying the additional cipher suites to support. You can also create a blacklist specifying the cipher suites to block.

Work with your network security administrator to determine the cipher suites that are suitable for the Informatica domain.

The list of cipher suites must be a comma-separated list. Use the Internet Assigned Numbers Authority (IANA) names for the cipher suites in the list. Alternatively, you can use a regular Java expression.

You configure the whitelist and blacklist with `infasetup`. You can provide the lists directly in command parameters or specify plain-text files that contain comma-separated lists.

The following sample text shows a list with two cipher suites:

```
TLS_RSA_WITH_AES_128_CBC_SHA256,TLS_RSA_WITH_3DES_EDE_CBC_SHA
```

You can configure the whitelist and blacklist of cipher suites for the Informatica domain when you create the domain. Use `infasetup` to create the Informatica domain, gateway nodes, and worker nodes. For more information about `infasetup` commands, see the *Informatica Command Reference*.

Alternatively, you can configure the whitelist and blacklist for an existing Informatica domain.

Configure the Informatica Domain with a New Effective List of Cipher Suites

To configure the cipher suites that the Informatica domain uses, you must update the Informatica domain, all gateway nodes, and all worker nodes with the same whitelist and blacklist.

Note: Changes to the blacklist, whitelist, and effective list are not cumulative. Informatica creates a new effective list based on the blacklist, default list, and whitelist when you run the command. The new effective list overwrites the previous list.

To configure an existing Informatica domain with a new effective list of cipher suites, perform the following steps:

1. Shutdown the Informatica domain.

2. Optionally, run the `infasetup listDomainCiphers` command to view the lists of cipher suites that a domain or node supports or blocks.

For example, run the following command to view all the cipher suite lists:

```
infasetup listDomainCiphers -l ALL -dc true
```

3. Run the `infasetup updateDomainCiphers` command on a gateway node and specify a whitelist, blacklist, or both.

For example, run the following command to add one cipher suite to the effective list and remove two cipher suites from the effective list:

```
infasetup updateDomainCiphers -cwl TLS_DHE_DSS_WITH_AES_128_CBC_SHA -cbl  
TLS_RSA_WITH_AES_128_CBC_SHA256,TLS_RSA_WITH_3DES_EDE_CBC_SHA
```

4. Run the `infasetup updateGatewayNode` command on each gateway node and specify a whitelist, blacklist, or both.

Use the same whitelist and blacklist as the domain.

For example, run the following command:

```
infasetup updateGatewayNode -cwl TLS_DHE_DSS_WITH_AES_128_CBC_SHA -cbl  
TLS_RSA_WITH_AES_128_CBC_SHA256,TLS_RSA_WITH_3DES_EDE_CBC_SHA
```

5. Update each worker node with the same set of cipher suites as the Informatica domain.

Use the same whitelist and blacklist as the domain.

For example, run the following command:

```
infasetup updateWorkerNode -cwl TLS_DHE_DSS_WITH_AES_128_CBC_SHA -cbl  
TLS_RSA_WITH_AES_128_CBC_SHA256,TLS_RSA_WITH_3DES_EDE_CBC_SHA
```

6. Start the Informatica domain.

7. Optionally, run the `infacmd isp listDomainCiphers` command to view the lists of cipher suites that a domain or node uses.

For example, run the following command to view the effective list of cipher suites that the domain uses:

```
infacmd isp listCiphers -l EFFECTIVE -dc true
```

Secure Sources and Targets

Informatica uses connection objects to connect to relational databases as source or target. You can create a connection object to a relational database that is secured with an SSL certificate.

You create PowerCenter connection objects in the Workflow Manager. You create Data Service , Data Quality, or Profiling connections in the Developer tool or in the Administrator tool.

You can create a connection to a secure source or target on the following databases:

- Oracle
- Microsoft SQL Server
- IBM DB2

Data Integration Service Sources and Targets

When you create a connection object for the Data Integration Service to process mappings, data profiles, scorecards, or SQL data services, you can define a connection to a database secured with the SSL protocol.

The Data Integration Service connects to the source or target database through JDBC drivers. When you configure the connection to a secure repository database, you must include the secure connection parameters in the JDBC connection string.

1. Set up a database secured with the SSL protocol to use as a source or target.
2. In the Administrator tool, create a connection.
3. In the **New Connection** dialog box, select the connection type. and click **OK**.

You can create a connection to a secure DB2, Microsoft SQL Server, or Oracle database.

4. In the **New Connection - Step 1 of 3** dialog box, enter the properties for the connection and click **Next**.
5. In the **New Connection - Step 2 of 3** page, enter the connection string to the database.

To connect to a secure database, enter the secure database parameters in the **Advanced JDBC Security Options** field. Informatica treats the value of the **Advanced JDBC Security Options** field as sensitive data and stores the parameter string encrypted.

The following list describes the secure database parameters:

EncryptionMethod

Required. Indicates whether data is encrypted when transmitted over the network. This parameter must be set to `SSL`.

ValidateServerCertificate

Optional. Indicates whether Informatica validates the certificate that the database server sends.

If this parameter is set to `True`, Informatica validates the certificate that the database server sends. If you specify the `HostNameInCertificate` parameter, Informatica also validates the host name in the certificate.

If this parameter is set to `False`, Informatica does not validate the certificate that the database server sends. Informatica ignores any truststore information that you specify.

Default is `True`.

HostNameInCertificate

Optional. Host name of the machine that hosts the secure database. If you specify a host name, Informatica validates the host name included in the connection string against the host name in the SSL certificate.

TrustStore

Required. Path and file name of the truststore file that contains the SSL certificate for the database.

TrustStorePassword

Required. Password for the truststore file for the secure database.

Note: Informatica appends the secure JDBC parameters to the connection string. If you include the secure JDBC parameters directly to the connection string, do not enter any parameters in the **Advanced JDBC Security Options** field.

6. Test the connection to verify that the connection to the secure database is valid.
7. Complete the process to create the relational connection.

PowerCenter Sources and Targets

When you create a connection object for a PowerCenter session, you can define a connection to a database secured with the SSL protocol.

You can connect to relational PowerCenter sources and targets through native connectivity or ODBC drivers.

If you connect to a secure relational source or target through native connectivity, verify that the database client contains the connection information for the secure database. For example, if you connect to a PowerCenter target on a secure Oracle database, configure the Oracle database client file *tnsnames.ora* with the connection information for the secure database.

If you connect to a secure relational source or target through ODBC drivers, verify that the database client contains the connection information for the secure database and the ODBC data source correctly defines the connection to the secure database.

Secure Data Storage

Informatica encrypts sensitive data, such as passwords and secure connection parameters, before it stores the data in the domain configuration repository. Informatica uses a keyword that you provide to create an encryption key with which to encrypt sensitive data.

During installation, you must provide a keyword for the installer to use to generate the encryption key for the domain. All nodes in a domain must use the same encryption key. If you install on multiple nodes, the installer uses the same encryption key for all nodes in the domain. For more information about generating an encryption key for the domain during installation, see the Informatica installation guides.

After installation, you can change the encryption key for the domain. Run the `infasetup` command to generate an encryption key and change the encryption key for the domain. After you change the encryption key for the domain, you must upgrade the content of the repositories in the domain to update the encrypted data.

Note: You must keep the name of the domain, the keyword for the encryption key, and the encryption key file in a secure location. The domain name, keyword, and encryption key are required when you change the encryption key for the domain or move a repository to another domain. If you lose the encryption key file, you need the keyword to generate the encryption key again. If you lose the keyword and encryption key, you cannot change the encryption key for the domain or move a repository to another domain.

Secure Directory on UNIX

When you install Informatica, the installer creates a directory to store Informatica files that require restricted access, such as the domain encryption key file. On UNIX, the installer assigns different permissions for the directory and the files in the directory.

By default, the installer creates the following directory within the Informatica installation directory to store the encryption key: `<INFA_HOME>/isp/config/keys`

The `/keys` directory contains the encryption key file for the node. If you configure the domain to use Kerberos authentication, the directory also contains the Kerberos keytab files.

During installation, you can specify a different directory in which to store the encryption file. The installer assigns the same permissions to the specified directory as the default directory.

The `/keys` directory and the files in the directory have the following permissions:

Directory Permissions

The owner of the directory has `-wx` permissions to the directory but no `r` permission. The owner of the directory is the user account used to run the installer. The group to which the owner belongs also has `-wx` permissions to the directory but no `r` permission.

For example, the user account *ediqa* owns the directory and belongs to the *infaadmin* group. The *ediqa* user account and the *infaadmin* group have the following permissions: `-wx-wx---`

The *ediqa* user account and the *infaadmin* group can write to and run files in the directory. They cannot display the list of files in directory but they can list a specific file by name.

If you know the name of a file in the directory, you can copy the file from the directory to another location. If you do not know the name of the file, you must change the permission for the directory to include the read permission before you can copy the file. You can use the command `chmod 730` to give read permission to the owner of the directory and subdirectories.

For example, you need to copy the encryption key file named *siteKey* to a temporary directory to make it accessible to another node in the domain. Run the command `chmod 730` on the `<Informatica installation directory>/isp/config` directory to assign the following permissions: `rwX-wX---`. You can then copy the encryption key file from the `/keys` subdirectory to another directory.

After you complete copying the files, change the permissions for the directory back to write and execute permissions. You can use the command `chmod 330` to remove the read permission.

Note: Do not use the `-R` option to recursively change the permissions for the directory and files. The directory and the files in the directory have different permissions.

File Permissions

The owner of the files in the directory has `rwX` permissions to the files. The owner of the files in the directory is the user account used to run the installer. The group to which the owner belongs also has `rwX` permissions to the files in the directory.

The owner and group have full access to the file and can display or edit the file in the directory.

Note: You must know the name of the file to be able to list or edit the file.

Changing the Encryption Key from the Command Line

After installation, you can change the encryption key for the domain from the command line. You must shut down the domain before you change the encryption key.

Use the `infasetup` command to generate an encryption key and configure the domain to use the new encryption key.

The following `infasetup` commands generate and change the encryption key:

generateEncryptionKey

Generates an encryption key in a file named *sitekey*. If the directory specified for the encryption key contains a file named *sitekey*, Informatica renames the file to *siteKey_old*.

migrateEncryptionKey

Changes the encryption key used to store sensitive data in the Informatica domain.

To change the encryption key for a domain, complete the following steps:

1. Shut down the domain.
2. Back up the domain before you change the encryption key.

To ensure that you can recover the domain if you encounter problems when you change the encryption key, back up the domain before you run the `infasetup` commands.

3. To generate an encryption key for the domain, run the `infasetup generateEncryptionKey` command. Specify the following options required to generate an encryption key:

Option	Argument	Description
-keyword -kw	keyword	The text string used as the base word from which to generate an encryption key. The keyword must meet the following criteria: <ul style="list-style-type: none">- From 8 to 20 characters long- Includes at least one uppercase letter- Includes at least one lowercase letter- Includes at least one number- Does not contain spaces
-domainName -dn	domain_name	Name of the Informatica domain.
-encryptionKeyLocation -kl	encryption_key_location	Directory that contains the current encryption key. The name of the encryption file is <i>sitekey</i> . Informatica renames the current <i>sitekey</i> file to <i>sitekey_old</i> and generates an encryption key in a new file named <i>sitekey</i> in the same directory.

4. To change the encryption key for the domain, run the `infasetup migrateEncryptionKey` command and specify the location of the old and new encryption key.

Specify the following options required to change the encryption key for the domain:

Option	Argument	Description
-LocationOfEncryptionKeys -loc	location_of_encryption_keys	<p>Directory in which the old encryption key file named <i>siteKey_old</i> and the new encryption key file named <i>siteKey</i> are stored.</p> <p>The directory must contain the old and new encryption key files. If the old and new encryption key files are stored in different directories, copy the encryption key files to the same directory.</p> <p>If the domain has multiple nodes, this directory must be accessible to any node in the domain where you run the <code>migrateEncryptionKey</code> command.</p> <p>Note: On UNIX, the file name <i>siteKey_old</i> is case-sensitive. If you manually rename the previous encryption key file, verify that the file name has the correct letter case.</p>
-IsDomainMigrated -mig	is_domain_migrated	<p>Indicates whether the domain has been updated to use the latest encryption key.</p> <p>When you run the <code>migrateEncryptionKey</code> command for the first time, set this option to <code>False</code> to indicate that the domain uses the old encryption key.</p> <p>After the first time, when you run the <code>migrateEncryptionKey</code> command to update other nodes in the domain, set this option to <code>True</code> to indicate that the domain has been updated to use the latest encryption key. Or, you can run the <code>migrateEncryptionKey</code> command without this option.</p> <p>Default is <code>True</code>.</p>

- Run the `infasetup` command on each node in the domain.

If the domain has multiple nodes, run `infasetup migrateEncryptionKey` on each node. Run the command on the gateway nodes before you run the command on the worker nodes. You can omit the `IsDomainMigrated` option after the first time you run the command.

- Restart the domain.

You must upgrade all repository services in the domain to update and encrypt sensitive data in the repositories with the new encryption key.

- Upgrade all Model Repository Services, PowerCenter Repository Services, and Metadata Manager Services.

You can upgrade a Model Repository Service and a PowerCenter Repository Service in the Administrator tool or at the command prompt. You can upgrade a Metadata Manager Service in the Administrator tool.

Note: The Metadata Manager Service must be disabled before you can upgrade it.

To upgrade a service in the Administrator tool, select **Manage > Upgrade** in the header area. If you select multiple services, the Administrator tool upgrades the services in the correct order.

To upgrade a service at the command prompt, use the following commands:

Repository Service Type	Command
Model Repository Service	<code>infacmd mrs UpgradeContents</code>
PowerCenter Repository Service	<code>pmrep Upgrade</code>

Application Services and Ports

Informatica domain services and application services in the Informatica domain have unique ports.

Informatica Domain

The following table describes the ports that you can set:

Port	Description
Service Manager port	Port number used by the Service Manager on the node. The Service Manager listens for incoming connection requests on this port. Client applications use this port to communicate with the services in the domain. The Informatica command line programs use this port to communicate to the domain. This is also the port for the SQL data service JDBC/ODBC driver. Default is 6006.
Service Manager Shutdown port	Port number that controls server shutdown for the domain Service Manager. The Service Manager listens for shutdown commands on this port. Default is 6007.
Informatica Administrator port	Port number used by Informatica Administrator. Default is 6008.
Informatica Administrator shutdown port	Port number that controls server shutdown for Informatica Administrator. Informatica Administrator listens for shutdown commands on this port. Default is 6009.
Minimum port number	Lowest port number in the range of dynamic port numbers that can be assigned to the application service processes that run on this node. Default is 6014.
Maximum port number	Highest port number in the range of dynamic port numbers that can be assigned to the application service processes that run on this node. Default is 6114.

Analyst Service

The following table lists the default port associated with the Analyst Service:

Type	Default Port
Analyst Service (HTTP)	8085
Analyst Service (HTTPS)	No default port. Enter the required port number when you create the service.
Analyst Service (Staging database)	No default port. Enter the database port number.

Content Management Service

The following table lists the default port associated with the Content Management Service:

Type	Default Port
Content Management Service (HTTP)	8105
Content Management Service (HTTPS)	No default port. Enter the required port number when you create the service.

Data Director Service

The following table lists the default port associated with the Data Director Service:

Type	Default Port
Data Director Service (HTTP)	No default port. Enter the required port number when you create the service.
Data Director Service (HTTPS)	No default port. Enter the required port number when you create the service.

Data Integration Service

The following table lists the default port associated with the Data Integration Service:

Type	Default Port
Data Integration Service (HTTP proxy)	8085
Data Integration Service (HTTP)	8095
Data Integration Service (HTTPS)	No default port. Enter the required port number when you create the service.
Profiling Warehouse database	No default port. Enter the database port number.
Human Task database	No default port. Enter the database port number.

Metadata Manager Service

The following table lists the default port associated with the Metadata Manager Service:

Type	Default Port
Metadata Manager Service (HTTP)	Default is 10250.
Metadata Manager Service (HTTPS)	No default port. Enter the required port number when you create the service.

PowerExchange® Listener Service

Use the same port number that you specify in the SVCNODE statement of the DBMOVER file.

If you define more than one Listener Service to run on a node, you must define a unique SVCNODE port number for each service.

PowerExchange Logger Service

Use the same port number that you specify in the SVCNODE statement of the DBMOVER file.

If you define more than one Listener Service to run on a node, you must define a unique SVCNODE port number for each service.

Web Services Hub Service

The following table lists the default port associated with the Web Services Hub Service:

Type	Default Port
Web Services Hub Service (HTTP)	7333
Web Services Hub Service (HTTPS)	7343

CHAPTER 6

Single Sign-on for Informatica Web Applications

This chapter includes the following topics:

- [SAML Authentication Overview, 82](#)
- [SAML Authentication Process, 82](#)
- [SAML-based Single Sign-on Setup, 83](#)

SAML Authentication Overview

You can configure Security Assertion Markup Language (SAML) authentication for Informatica web applications.

Security Assertion Markup Language is an XML-based data format for exchanging authentication information between a service provider and an identity provider. In an Informatica domain, the Informatica web application is the service provider. Microsoft Active Directory Federation Services (AD FS) 2.0 is the identity provider, which authenticates web application users with your organization's LDAP or Active Directory identity store.

Note: SAML authentication cannot be used in an Informatica domain configured to use Kerberos authentication.

SAML Authentication Process

Informatica web applications and the identity provider exchange authentication information to enable SAML authentication in an Informatica domain.

The following steps describe the basic SAML authentication flow:

1. A user accesses an Informatica web application.
2. The user selects the security domain containing LDAP user accounts used for SAML authentication on the application log in page, and then clicks the log in button.

If the user selects the native security domain, the user provides a user name and password and logs in to the application.

3. Based on the identity provider configuration, the user is prompted to provide the credentials required for first time authentication.
4. The identity provider validates the user's credentials and creates a session for the user.
The identity provider also validates the target web application URL, and then redirects the user to the web application with a SAML token containing the user's identity information.
5. The application validates the SAML token and user identity information, creates a user session, and then completes the user log in process.

The existing user session in the browser is used for subsequent authentication. To access another Informatica web application configured to use SAML authentication, the user selects the LDAP security domain on the application log in page. The user does not need to supply a user name or password.

The user remains logged in to all Informatica web applications that are running in the same browser session. However, if the user logs out of an Informatica web application, the user is also logged out of other Informatica web applications running in the same browser session.

SAML-based Single Sign-on Setup

Configure Active Directory Federation Services (AD FS) and the Informatica domain to use SAML-based single sign-on.

To configure SAML-based single sign-on for supported Informatica web applications, perform the following tasks:

1. Create an LDAP security domain for Informatica web application user accounts, and then import the users into the domain from Active Directory.
2. Export the Identity Provider Assertion Signing Certificate from AD FS.
3. Import the Identity Provider Assertion Signing certificate into the Informatica default truststore file on each gateway node in the domain.
4. Add Informatica as a relying party trust in AD FS and map LDAP attributes to the corresponding types used in security tokens issued by AD FS.
5. Add the URL for each Informatica web application to AD FS.
6. Enable single-sign on for Informatica web applications within the Informatica domain.

Before You Enable Single Sign-on

Ensure the Windows network and Informatica domain gateway nodes are configured to use single sign-on.

Validate the following requirements to ensure that the Informatica domain can use single sign-on:

Verify that the required services are deployed and configured on the Windows network.

Single sign-on requires the following services:

- Microsoft Active Directory
- Microsoft Active Directory Federation Services 2.0

Ensure the Informatica web application services use secure HTTPS connections.

By default, AD FS requires that web application URLs use the HTTPS protocol.

Ensure that the system clocks on the AD FS host and all gateway nodes in the domain are synchronized.

The lifetime of SAML tokens issued by AD FS is set according to the AD FS host system clock. Ensure that the system clocks on the AD FS host and all gateway nodes in the domain are synchronized.

To avoid authentication issues, the lifetime of a SAML token issued by AD FS is valid if the start time or end time set in the token is within 120 seconds of a gateway node's system time.

Step 1. Create a Security Domain for Web Application User Accounts

Create a security domain for web application user accounts that will use SAML-based single-sign on, and then import each user's LDAP account from Active Directory into the domain.

You must import the LDAP accounts for all users that use SAML-based single-sign on to access the Administrator tool, the Analyst tool, and the Monitoring tool into the security domain. After importing the accounts into the domain, assign the appropriate Informatica domain roles, privileges and permissions to the accounts within the LDAP security domain.

1. In the Administrator tool, click the **Users** tab, and then select the **Security** view.
2. Click the **Actions** menu and select **LDAP Configuration**.
The **LDAP Configuration** dialog box opens.
3. Click the **LDAP Connectivity** tab.
4. Configure the connection properties for the Active Directory server.

The following table describes the server connection properties:

Property	Description
Server Name	Host name or IP address of the Active Directory server.
Port	Listening port for the server. The default value is 389.
LDAP Directory Service	Select Microsoft Active Directory.
Name	Distinguished name (DN) for the principal LDAP user. The user name often consists of a common name (CN), an organization (O), and a country (C). The principal user name is an administrative user with access to the directory. Specify a user that has permission to read other user entries in the directory service.
Password	Password for the principal LDAP user.
Use SSL Certificate	Indicates that the LDAP server uses the Secure Socket Layer (SSL) protocol. If the LDAP server uses SSL, you must import the certificate into a truststore file on every gateway node within the Informatica domain. You must also set the INFA_TRUSTSTORE and INFA_TRUSTSTORE_PASSWORD environment variables if you do not import the certificate into the default Informatica truststore.
Trust LDAP Certificate	Determines whether the Service Manager can trust the SSL certificate of the LDAP server. If selected, the Service Manager connects to the LDAP server without verifying the SSL certificate. If not selected, the Service Manager verifies that the SSL certificate is signed by a certificate authority before connecting to the LDAP server.

Property	Description
Not Case Sensitive	Indicates that the Service Manager must ignore case sensitivity for distinguished name attributes when assigning users to groups. Enable this option.
Group Membership Attribute	Name of the attribute that contains group membership information for a user. This is the attribute in the LDAP group object that contains the distinguished names (DNs) of the users or groups who are members of a group. For example, <i>member</i> or <i>memberof</i> .
Maximum size	Maximum number of user accounts to import into a security domain. If the number of user to be imported exceeds the value for this property, the Service Manager generates an error message and does not import any user. Set this property to a higher value if you have many users to import. The default value is 1000.

The following image shows the connection details for an LDAP server set in the LDAP Connectivity panel of the **LDAP Configuration** dialog box.

LDAP Configuration

Fields marked with an asterisk (*) are required.

LDAP Connectivity | Security Domains | Schedule

Server name and port for the LDAP server

Server Name *

Port *

LDAP Directory Service *

Distinguished name and password of the principal user (Leave blank for anonymous login)

Name

Password

☐ Modify Password

SSL certificate for the LDAP server

☒ Use SSL Certificate

☐ Trust LDAP Certificate

☐ Not Case Sensitive

Group attribute definition

Group Membership Attribute

Maximum number of users to import for a security domain

Maximum size *

- Click **Test Connection** to verify that the connection to the Active Directory server is valid.
- Click the **Security Domains** tab.
- Click **Add** to create a security domain.
- Enter the security domain properties.

The following table describes the security domain properties:

Property	Description
Security Domain	<p>Name of the LDAP security domain. The name is not case sensitive and must be unique within the domain. The name cannot exceed 128 characters or contain the following special characters: , + / < > @ ; \ % ?</p> <p>The name can contain an ASCII space character except for the first and last character. All other space characters are not allowed.</p>
User search base	<p>Distinguished name (DN) of the entry that serves as the starting point to search for user names in the LDAP directory service. The search finds an object in the directory according to the path in the distinguished name of the object.</p> <p>In Active Directory, the distinguished name of a user object might be cn=UserName,ou=OrganizationalUnit,dc=DomainName, where the series of relative distinguished names denoted by dc=DomainName identifies the DNS domain of the object.</p>
User filter	<p>An LDAP query string that specifies the criteria for searching for users in Active Directory. The filter can specify attribute types, assertion values, and matching criteria.</p> <p>For Active Directory, format the query string as: sAMAccountName=<account></p>
Group search base	<p>Distinguished name (DN) of the entry that serves as the starting point to search for group names in Active Directory.</p>
Group filter	<p>An LDAP query string that specifies the criteria for searching for groups in the directory service.</p>

The following image shows the properties for an LDAP security domain named SAML_USERS set in the Security Domains panel of the **LDAP Configuration** dialog box. The user filter is set to import all users beginning with the letter "s".

LDAP Configuration

Fields marked with an asterisk (*) are required.

LDAP Connectivity **Security Domains** Schedule

You can specify multiple security domains for LDAP users and groups. Click Add to add a new security domain. + Add

Add new Security Domain Preview Cancel

Security Domain *	SAML_USERS
User search base	CN=USERS,DC=PLATFORMKRB,DC=COM
User filter	samAccountName=s*
Group search base	
Group filter	

? Synchronize Now OK Cancel

9. Click **Synchronize Now**.
The security domain appears in the Users view.
10. Expand the domain in the Navigator to view the imported user accounts.
11. Set the appropriate roles, privileges, and permissions on the user accounts that will access each web application.


Step 2. Export the Certificate from AD FS

Export the Assertion Signing certificate from AD FS.

The certificate is a standard X.509 certificate used to sign the assertions within the SAML tokens that AD FS issues to Informatica web applications. You can generate a self-signed Secure Sockets Layer (SSL) certificate for AD FS, or you can get a certificate from a certificate authority and import it into AD FS.


1. Log in to the AD FS Management Console.
2. Expand the **Service > Certificates** folder.

3. Right-click the certificate under Token-signing in the Certificates pane, and then select **View Certificate**, as shown in the following image:




The **Certificate** dialog appears.

4. Click the **Details** tab, and then click **Copy to File**, as shown in the following image:



The **Certificate Export Wizard** appears.

5. Select **DER encoded binary X.509 (.CER)** as the format, as shown in the following image:



6. Click **Next**.
7. Enter the certificate file name and the location to export it to, and click **Next**.
8. Click **OK**, and then click **Finish** to complete the export.

Step 3. Import the Certificate into the Informatica Truststore

Import the Assertion Signing certificate into the default Informatica truststore file on every gateway node within the Informatica domain.

Use the Java keytool key and certificate management utility to import the certificate into the Informatica truststore file. The default truststore file, `infa_truststore.jks`, is installed in the following directory on each node:

```
<Informatica installation directory>\services\shared\security\
```

1. Copy the certificate files to a local folder on a gateway node within the Informatica domain.
2. From the command line, go to the location of the keytool utility on the node:

```
<Informatica installation directory>\java\jre\bin
```
3. From the command line, run the following command:

```
keytool -importcert -alias <certificate alias name> -file <certificate path>\<certificate filename> -keystore <Informatica installation directory>\services\shared\security\infa_truststore.jks -storepass <password>
```

Include the password for the Informatica default truststore.

4. Restart the node.

Step 4. Configure Active Directory Federation Services


Configure AD FS to issue SAML tokens to Informatica web applications.

Use the AD FS Management Console to perform the following tasks:

- Add Informatica as a relying party trust in AD FS. The relying party trust definition enables AD FS to accept authentication requests from Informatica web applications.
- Edit the Send LDAP Attributes as Claims rule to map LDAP attributes in your identity store to the corresponding types used in SAML tokens issued by AD FS.

Note: All strings are case sensitive in AD FS, including URLs.

1. Log in to the AD FS Management Console.
2. Expand the **Trust Relationships > Relying Party Trusts** folder.
3. Right-click the **Relying Party Trusts** folder and select **Add Relying Party Trust** as shown in the following image:



The **Add Relying Party Trust Wizard** appears.

4. Click **Start**.


The **Select Data Source** panel appears.

5. Click **Enter data about the relying party manually** as shown in the following image:

The screenshot shows the 'Add Relying Party Trust Wizard' dialog box, specifically the 'Select Data Source' step. The 'Steps' pane on the left lists the following steps: Welcome, Select Data Source (highlighted), Specify Display Name, Choose Profile, Configure Certificate, Configure URL, Configure Identifiers, Choose Issuance Authorization Rules, Ready to Add Trust, and Finish. The main area contains the instruction: 'Select an option that this wizard will use to obtain data about this relying party:'. There are three radio button options: 1. 'Import data about the relying party published online or on a local network.' with a description: 'Use this option to import the necessary data and certificates from a relying party organization that publishes its federation metadata online or on a local network.' It includes a text field for 'Federation metadata address (host name or URL):' with an example: 'fs.contoso.com or https://www.contoso.com/app'. 2. 'Import data about the relying party from a file.' with a description: 'Use this option to import the necessary data and certificates from a relying party organization that has exported its federation metadata to a file. Ensure that this file is from a trusted source. This wizard will not validate the source of the file.' It includes a text field for 'Federation metadata file location:' and a 'Browse...' button. 3. 'Enter data about the relying party manually' (selected) with a description: 'Use this option to manually input the necessary data about this relying party organization.' At the bottom are buttons for '< Previous', 'Next >', 'Cancel', and 'Help'.

6. Click **Next**
7. Enter "Informatica" as the display name, and then click **Next**.

8. Click **AD FS 2.0 profile** as shown in the following image:




9. Click **Next**.
Skip the certificate configuration panel in the wizard.

10. Check **Enable support for the SAML WebSSO protocol**, then enter the complete URL for the Administrator tool, as shown in the following image:

The screenshot shows the 'Add Relying Party Trust Wizard' dialog box, specifically the 'Configure URL' step. The 'Steps' pane on the left lists the following steps: Welcome, Select Data Source, Specify Display Name, Choose Profile, Configure Certificate, Configure URL (highlighted), Configure Identifiers, Choose Issuance Authorization Rules, Ready to Add Trust, and Finish. The main area contains instructions: 'AD FS 2.0 supports the WS-Trust, WS-Federation and SAML 2.0 WebSSO protocols for relying parties. If WS-Federation, SAML, or both are used by the relying party, select the check boxes for them and specify the URLs to use. Support for the WS-Trust protocol is always enabled for a relying party.' There are two sections for configuration. The first section, 'Enable support for the WS-Federation Passive protocol', is unchecked. It includes a text box for 'Relying party WS-Federation Passive protocol URL:' with an example: 'https://fs.contoso.com/adfs/ls/'. The second section, 'Enable support for the SAML 2.0 WebSSO protocol', is checked. It includes a text box for 'Relying party SAML 2.0 SSO service URL:' with the value 'https://infaserver:6107/administrator/' entered and an example: 'https://www.contoso.com/adfs/ls/'. At the bottom are buttons for '< Previous', 'Next >', 'Cancel', and 'Help'.


11. Click **Next**.
12. Enter "Informatica" in the Relying party trust identifier field. Click **Add**, and then click **Next**.

13. Select **Permit all users to access the relying party** as shown in the following image:




14. Click **Next**.

15. Check **Open the Edit Claim Rules dialog for this relying party trust when the wizard closes** as shown in the following image:



16. Click **Close**.
The **Edit Claim Rules for Informatica** dialog box appears.
17. Click **Add Rule**.
The **Add Transform Claim Rule Wizard** opens.
18. Select **Send LDAP Attributes as Claims** from the menu, as shown in the following image:



19. Click **Next**.

20. Enter any string as the claim rule name, as shown in the image below:

The screenshot shows the 'Add Transform Claim Rule Wizard' dialog box, specifically the 'Configure Rule' step. The 'Steps' pane on the left shows 'Choose Rule Type' and 'Configure Claim Rule'. The main area contains the following fields and options:

- Claim rule name:** A text box containing 'MyRule'.
- Rule template:** A dropdown menu showing 'Send LDAP Attributes as Claims'.
- Attribute store:** A dropdown menu showing 'Active Directory'.
- Mapping of LDAP attributes to outgoing claim types:** A table with two columns: 'LDAP Attribute' and 'Outgoing Claim Type'.

	LDAP Attribute	Outgoing Claim Type
▶	SAM-Account-Name	username
*		

At the bottom of the dialog are buttons for '< Previous', 'Finish', 'Cancel', and 'Help'.

21. Select Active Directory from the **Attribute store** menu.
22. Select SAM-Account-Name from the **LDAP Mapping** menu.
23. Enter "username" in the **Outgoing Claim Type** field.
24. Click **Finish**, then click **OK** to close the wizard.

Step 5. Add Informatica Web Application URLs to AD FS


Add the URL for each Informatica web application using single sign-on to AD FS.

You provide the URL for an Informatica Web application to enable AD FS to accept authentication requests sent by the application. Providing the URL also enables AD FS to send the SAML token to the application after authenticating the user.

You do not need to add the URL for the Administrator tool, since you already entered it as part of configuring AD FS.

1. Log in to the AD FS Management Console.
2. Expand the **Trust Relationships > Relying Party Trusts** folder.

3. Right-click the **Informatica** entry and select **Properties**, as shown in the image below:




The **Informatica Properties** dialog box appears.

4. Click the **Endpoints** tab.

The **Add an Endpoint** dialog box appears.

5. Select **SAML Assertion Consumer** from the **Endpoint type** menu, then select **POST** from the **Binding** menu, as shown in the image below:



6. Enter the complete URL for a supported Informatica web application, then click **OK**. Repeat this procedure for each web application.

Step 6. Enable SAML-based Single Sign-on

You can enable SAML-based single sign-on in an existing Informatica domain, or you can enable it when you install or create a domain.

Select one of the following options:

Enable single-sign on when you install the Informatica services.

You can enable SAML-based single sign-on and specify the identity provider URL when you configure the domain as part of the installation process.

Enable single sign-on in an existing domain.

Use the `infasetup updateSamIConfig` command to enable single sign-on in an existing Informatica domain. You can run the command on any gateway node within the domain.

Shut down the domain before you run the command.

Specify the identity provider URL as the value for the `-iu` option. The following example shows the command usage:

```
infasetup updateSamlConfig -saml true -iu https://server.company.com/adfs/ls/
```

Enable single sign-on when you create a domain.

Use the `infasetup defineDomain` command to enable single sign-on when you create a domain.

The following example shows the SAML options as the final two options on the command line:

```
infasetup defineDomain -dn TestDomain -nn TestNode1 -na host1.company.com -cs
"jdbc:informatica:oracle://host:1521;sid=xxxx" -du test_user -dp test_user -dt oracle -rf
$HOME/ISP/BIN/nodeoptions.xml -ld $HOME/ISP/1011/source/logs -mi 10000 -ma 10200 -ad
test_admin -pd test_admin -saml true -iu https://server.company.com/adfs/ls/
```

infasetup Command Options

Set the SAML options in the `infasetup updateSamlConfig` command to enable single sign-on in a domain or in the `infasetup defineDomain` command when you create a domain.

The following table describes the options and arguments:

Option	Argument	Description
<code>-EnableSaml</code> <code>-saml</code>	true false	Required. Set this value to true to enable SAML-based single sign-on for supported Informatica web applications within the Informatica domain. Set this value to false to disable SAML-based SSO for supported Informatica web applications within the Informatica domain.
<code>-IdpUrl</code> <code>-iu</code>	identity_provider_url	Required if the <code>-saml</code> option is true. Specify the identity provider URL for the domain. You must specify the complete URL string.

See the *Informatica Command Reference* for instructions on using the `infasetup updateSamlConfig` and `infasetup defineDomain` commands.

Getting the Identity Provider URL

You must provide the SAML 2.0/WS-Federation URL for the AD FS server to enable single sign-on.

You set this URL as the value for the `-iu` option when you run the `infasetup updateSamlConfig` command or the `infasetup defineDomain` command. Use Windows PowerShell on the AD FS server to get the URL.

1. Open the Windows PowerShell command prompt window on the AD FS server. Select the Run as administrator option when you open the command prompt.
2. Type the following command at the Windows PowerShell command prompt:

```
Get-ADFSEndpoint
```

3. Find the FullUrl value returned for the SAML 2.0/WS-Federation protocol, as shown in the image below:

```
ClientCredentialType : Anonymous
Enabled              : True
FullUrl              : https://adfs.company.com/adfs/ls/
Proxy                : False
Protocol             : SAML 2.0/WS-Federation
SecurityMode         : Transport
AddressPath          : /adfs/ls/
Version              : default
```

CHAPTER 7

Security Management in Informatica Administrator

This chapter includes the following topics:

- [Using Informatica Administrator Overview, 103](#)
- [User Security, 104](#)
- [Security Tab, 107](#)
- [Password Management, 109](#)
- [Domain Security Management, 110](#)
- [User Security Management, 110](#)

Using Informatica Administrator Overview

Informatica Administrator is the tool that you use to manage the Informatica domain and Informatica security.

Use the Administrator tool to complete the following types of tasks:

- Domain administrative tasks. Manage logs, domain objects, user permissions, and domain reports. Generate and upload node diagnostics. Monitor Data Integration Service jobs and applications. Domain objects include application services, nodes, grids, folders, database connections, operating system profiles, and licenses.
- Domain administrative tasks. Manage logs, domain objects, and user permissions. Monitor Data Integration Service jobs and applications.
- Domain administrative tasks. Manage logs, domain objects, and user permissions.
- Security administrative tasks. Manage users, groups, roles, and privileges.

Note: If you have PowerCenter Express Personal Edition, you do not have access to the security features.

The Administrator tool has the following tabs:

- **Manage.** View and edit the properties of the domain and objects within the domain.
- **Monitor.** View the status of profile jobs, scorecard jobs, preview jobs, mapping jobs, SQL data services, web services, and workflows for each Data Integration Service.
- **Monitor.** View the status of profile jobs, preview jobs, mapping jobs, SQL data services, and web services for each Data Integration Service.

- **Monitor.** View the status of profile jobs, preview jobs, mapping jobs, and workflows for the Data Integration Service.
- **Monitor.** View and monitor Ultra Messaging deployments.
- **Logs.** View log events for the domain and services within the domain.
- **Reports.** Run a Web Services Report or License Management Report.
- **Security.** Manage users, groups, roles, and privileges.
- **Security.** Manage users, groups, roles, and privileges. If you have PowerCenter Express Personal Edition, you do not have access to the Security tab.
- **Cloud.** View information about your Informatica Cloud® organization.

The Administrator tool has the following header items:

- **Log out.** Log out of the Administrator tool.
- **Manage.** Manage your account.
- **Help.** Access help for the current tab and determine the Informatica version.
- **Help.** Access help for the current tab, determine the Informatica version, and configure the data usage policy.

User Security

The Service Manager and some application services control user security in application clients. Application clients include Informatica Administrator, Informatica Analyst, Informatica Developer, Metadata Manager, and PowerCenter Client. The Service Manager and some application services control user security in application clients. Application clients include Informatica Administrator and Informatica Developer. The Service Manager and some application services control user security in application clients. Application client includes Informatica Administrator.

The Service Manager and application services control user security by performing the following functions:

Encryption

When you log in to an application client, the Service Manager encrypts the password.

Authentication

When you log in to an application client, the Service Manager authenticates your user account based on your user name and password or on your user authentication token.

Authorization

When you request an object in an application client, the Service Manager and some application services authorize the request based on your privileges, roles, and permissions.

You can also use HTTPS for secure connection to the domain and the application services. The following application services provide HTTPS connection along with the Informatica domain:

- Data Integration Service
- Analyst Service
- Content Management Service
- Metadata Manager Service
- Web Service Hub Service

You can also use HTTPS for secure connection to the domain and the application services. The following application services support HTTPS connection along with the Informatica domain:

- Data Integration Service
- Analyst Service

You can also use HTTPS for secure connection to the domain and the application services.

Encryption

Informatica encrypts passwords sent from application clients to the Service Manager. Informatica uses AES encryption with multiple 128-bit keys to encrypt passwords and stores the encrypted passwords in the domain configuration database. Configure HTTPS to encrypt passwords sent to the Service Manager from application clients.

Authentication

The Service Manager authenticates users who log in to application clients.

The first time you log in to an application client, you enter a user name, password, and security domain. A security domain is a collection of user accounts and groups in an Informatica domain.

The security domain that you select determines the authentication method that the Service Manager uses to authenticate your user account:

- Native. When you log in to an application client as a native user, the Service Manager authenticates your user name and password against the user accounts in the domain configuration database.
- Lightweight Directory Access Protocol (LDAP). When you log in to an application client as an LDAP user, the Service Manager passes your user name and password to the external LDAP directory service for authentication.

When you log in to an application client as a native user, the Service Manager authenticates your user name and password against the user accounts in the domain configuration database.

When you log in to an application client as a native user, the Service Manager authenticates your user name and password against the user accounts in the domain configuration database.

Single Sign-On

After you log in to an application client, the Service Manager allows you to launch another application client or to access multiple repositories within the application client. You do not need to log in to the additional application client or repository.

The first time the Service Manager authenticates your user account, it creates an encrypted authentication token for your account and returns the authentication token to the application client. The authentication token contains your user name, security domain, and an expiration time. The Service Manager periodically renews the authentication token before the expiration time.

When you access multiple repositories within an application client, the application client sends the authentication token to the Service Manager for user authentication.

When you launch one web application client from another one, the application client passes the authentication token to the next application client. The next web application client sends the authentication token to the Service Manager for user authentication. You must log out of each web application client separately. For example, if you open the Analyst tool from the Administrator tool, you must log out of the Analyst tool and the Administrator tool separately.

Note: To use single sign-on between the Administrator tool, the Analyst tool, and the Monitoring tool, you must add their fully qualified domain names to the host file for every node.

You cannot use single sign-on to connect to a web application client from a client tool. For example, if you launch the Administrator tool from the Developer tool, you must log in to the Administrator tool.

Authorization

The Service Manager authorizes user requests for domain objects. Requests can come from the Administrator tool. The following application services authorize user requests for other objects:

- Data Integration Service
- Metadata Manager Service
- Model Repository Service
- PowerCenter Repository Service

The Service Manager authorizes user requests for domain objects. Requests can come from the Administrator tool. The following application services authorize user requests for other objects:

- Data Integration Service
- Model Repository Service

When you create native users and groups or import LDAP users and groups, the Service Manager stores the information in the domain configuration database into the following repositories:

- Model repository
- PowerCenter repository
- PowerCenter repository for Metadata Manager

The Service Manager synchronizes the user and group information between the repositories and the domain configuration database when the following events occur:

- You restart the Metadata Manager Service, Model Repository Service, or PowerCenter Repository Service.
- You add or remove native users or groups.
- The Service Manager synchronizes the list of LDAP users and groups in the domain configuration database with the list of users and groups in the LDAP directory service.

The Service Manager synchronizes the user and group information between the repositories and the domain configuration database when the following events occur:

- You restart the Model Repository Service.
- You add or remove native users or groups.

When you assign permissions to users and groups in an application client, the application service stores the permission assignments with the user and group information in the appropriate repository.

When you request an object in an application client, the appropriate application service authorizes your request. For example, if you try to edit a project in Informatica Developer, the Model Repository Service authorizes your request based on your privilege, role, and permission assignments.

Security Tab

You administer Informatica security on the Security tab of the Administrator tool.

The Security tab has the following components:

- Search section. Search for users, groups, or roles by name.
- Navigator. The Navigator appears in the left pane and displays groups, users, and roles.
- Contents panel. The contents panel displays properties and options based on the object selected in the Navigator and the tab selected in the contents panel.
- Security Actions menu. Contains options to create or delete a group, user, or role. You can manage LDAP and operating system profiles. You can also view users that have privileges for a service.

Note: If you have PowerCenter Express Personal Edition, you do not have access to the Security tab

Using the Search Section

Use the Search section to search for users, groups, and roles by name. Search is not case sensitive.

1. In the Search section, select whether you want to search for users, groups, or roles.
2. Enter the name or partial name to search for.

You can include an asterisk (*) in a name to use a wildcard character in the search. For example, enter "ad*" to search for all objects starting with "ad". Enter "*ad" to search for all objects ending with "ad".

3. Click Go.

The Search Results section appears and displays a maximum of 100 objects. If your search returns more than 100 objects, narrow your search criteria to refine the search results.

4. Select an object in the Search Results section to display information about the object in the contents panel.

Using the Security Navigator

The Navigator appears in the contents panel of the Security tab. When you select an object in the Navigator, the contents panel displays information about the object.

The Navigator on the Security tab displays one of the following sections based on what you are viewing:

- Groups section. Select a group to view the properties of the group, the users assigned to the group, and the roles and privileges assigned to the group.
- Users section. Select a user to view the properties of the user, the groups the user belongs to, and the roles and privileges assigned to the user.
- Roles section. Select a role to view the properties of the role, the users and groups that have the role assigned to them, and the privileges assigned to the role.

The Navigator provides different ways to complete a task. You can use any of the following methods to manage groups, users, and roles:

- Click the Actions menu. Each section of the Navigator includes an Actions menu to manage groups, users, or roles. Select an object in the Navigator and click the Actions menu to create, delete, or move groups, users, or roles.
- Right-click an object. Right-click an object in the Navigator to display the create, delete, and move options available in the Actions menu.
- Use keyboard shortcuts. Use keyboard shortcuts to move to different sections of the Navigator.

Groups

A group is a collection of users and groups that can have the same privileges, roles, and permissions.

The Groups section of the Navigator organizes groups into security domain folders. A security domain is a collection of user accounts and groups in an Informatica domain. Native authentication uses the Native security domain which contains the users and groups created and managed in the Administrator tool. LDAP authentication uses LDAP security domains which contain users and groups imported from the LDAP directory service.

The Groups section of the Navigator organizes groups into security domain folders. A security domain is a collection of user accounts and groups in an Informatica domain. Native authentication uses the Native security domain which contains the users and groups created and managed in the Administrator tool.

The Groups section of the Navigator organizes groups into security domain folders. A security domain is a collection of user accounts and groups in an Informatica domain. Native authentication uses the Native security domain which contains the users and groups created and managed in the Administrator tool.

When you select a security domain folder in the Groups section of the Navigator, the contents panel displays all groups belonging to the security domain. Right-click a group and select **Navigate to Item** to display the group details in the contents panel.

When you select a group in the Navigator, the contents panel displays the following tabs:

- **Overview.** Displays general properties of the group and users assigned to the group.
- **Privileges.** Displays the privileges and roles assigned to the group for the domain and for application services in the domain.

Users

A user with an account in the Informatica domain can log in to the following application clients:

- Informatica Administrator
- PowerCenter Client
- Metadata Manager
- Informatica Developer
- Informatica Analyst

A user with an account in the Informatica domain can log in to the following application clients:

- Informatica Administrator
- Informatica Developer

A user with an account in the Informatica domain can log in to Informatica Administrator.

The Users section of the Navigator organizes users into security domain folders. A security domain is a collection of user accounts and groups in an Informatica domain. Native authentication uses the Native security domain which contains the users and groups created and managed in the Administrator tool. LDAP authentication uses LDAP security domains which contain users and groups imported from the LDAP directory service.

The Users section of the Navigator organizes users into security domain folders. A security domain is a collection of user accounts and groups in an Informatica domain.

The Users section of the Navigator organizes users into security domain folders. A security domain is a collection of user accounts and groups in an Informatica domain.

When you select a security domain folder in the Users section of the Navigator, the contents panel displays all users belonging to the security domain. Right-click a user and select **Navigate to Item** to display the user details in the contents panel.

When you select a user in the Navigator, the contents panel displays the following tabs:

- **Overview.** Displays general properties of the user and all groups to which the user belongs.
- **Privileges.** Displays the privileges and roles assigned to the user for the domain and for application services in the domain.

Roles

A role is a collection of privileges that you assign to a user or group. Privileges determine the actions that users can perform. You assign a role to users and groups for the domain and for application services in the domain.

The Roles section of the Navigator organizes roles into the following folders:

- **System-defined Roles.** Contains roles that you cannot edit or delete. The Administrator role is a system-defined role.
- **Custom Roles.** Contains roles that you can create, edit, and delete. The Administrator tool includes some custom roles that you can edit and assign to users and groups.

When you select a folder in the Roles section of the Navigator, the contents panel displays all roles belonging to the folder. Right-click a role and select **Navigate to Item** to display the role details in the contents panel.

When you select a role in the Navigator, the contents panel displays the following tabs:

- **Overview.** Displays general properties of the role and the users and groups that have the role assigned for the domain and application services.
- **Privileges.** Displays the privileges assigned to the role for the domain and application services.

Password Management

You can change the password through the Change Password application.

You can open the Change Password application from the Administrator tool or with the following URL:

`http://<fully qualified host name>:<port>/passwordchange/`

The Service Manager uses the user password associated with a worker node to authenticate the domain user. If you change a user password that is associated with one or more worker nodes, the Service Manager updates the password for each worker node. The Service Manager cannot update nodes that are not running. For nodes that are not running, the Service Manager updates the password when the nodes restart.

Note: For an LDAP user account, change the password in the LDAP directory service.

Changing Your Password

Change the password for a native user account at any time. For a user account created by someone else, change the password the first time you log in to the Administrator tool.

1. In the Administrator tool header area, click **Manage > Change Password**.

The Change Password application opens in a new browser window.

2. Enter the current password in the **Password** box, and the new password in the **New Password** and **Confirm Password** boxes.
3. Click **Update**.

Domain Security Management

You can configure Informatica domain components to use the Secure Sockets Layer (SSL) protocol or the Transport Layer Security (TLS) protocol to encrypt connections with other components. When you enable SSL or TLS for domain components, you ensure secure communication.

You can configure secure communication in the following ways:

Between services within the domain

You can configure secure communication between services within the domain.

Between the domain and external components

You can configure secure communication between Informatica domain components and web browsers or web service clients.

Each method of configuring secure communication is independent of the other methods. When you configure secure communication for one set of components, you do not need to configure secure communication for any other set.

Note: If you change a secure domain to a non-secure domain or from a non-secure domain to a secure domain, you must delete the domain configuration in the Developer tool and PowerCenter client tools and configure the domain again in the client.

User Security Management

You manage user security within the domain with privileges and permissions.

Privileges determine the actions that users can complete on domain objects. Permissions define the level of access a user has to a domain object. Domain objects include the domain, folders, nodes, grids, licenses, database connections, operating system profiles, and application services.

Privileges determine the actions that users can complete on domain objects. Permissions define the level of access a user has to a domain object. Domain objects include the domain, node, license, database connections, and application services.

Even if a user has the domain privilege to complete certain actions, the user might also require permission to complete the action on a particular object. For example, a user has the Manage Services domain privilege which grants the user the ability to edit application services. However, the user also must have permission on the application service. A user with the Manage Services domain privilege and permission on the Development Repository Service but not on the Production Repository Service can edit the Development Repository Service but not the Production Repository Service.

Even if a user has the domain privilege to complete certain actions, the user might also require permission to complete the action on a particular object.

To log in to the Administrator tool, a user must have the Access Informatica Administrator domain privilege. If a user has the Access Informatica Administrator privilege and permission on an object, but does not have

the domain privilege that grants the ability to modify the object type, then the user can view the object. For example, if a user has permission on a node, but does not have the Manage Nodes and Grids privilege, the user can view the node properties but cannot configure, shut down, or remove the node.

To log in to the Administrator tool, a user must have the Access Informatica Administrator domain privilege. If a user has the Access Informatica Administrator privilege and permission on an object, but does not have the domain privilege that grants the ability to modify the object type, then the user can view the object.

If a user does not have permission on a selected object in the Navigator, the contents panel displays a message indicating that permission on the object is denied.

CHAPTER 8

Users and Groups

This chapter includes the following topics:

- [Users and Groups OverviewUsers and Groups, 112](#)
- [Default Groups, 113](#)
- [Understanding User Accounts, 114](#)
- [Managing Users, 116](#)
- [Managing Groups, 124](#)
- [Managing Operating System Profiles, 126](#)
- [Account Lockout, 133](#)

Users and Groups OverviewUsers and Groups

To access the application services and objects in the Informatica domain and to use the application clients, you must have a user account. The tasks you can perform depend on the type of user account you have and the type of PowerCenter Express license.

To access the application services and objects in the Informatica domain and to use the application clients, you must have a user account.

During installation, a default administrator user account is created. Use the default administrator account to log in to the Informatica domain and manage application services, domain objects, and other user accounts. When you log in to the Informatica domain after installation, change the password to ensure security for the Informatica domain and applications.

Note: If you install PowerCenter Express Personal Edition you must use the default administrator account for all operations. You cannot create users or groups and manage permissions.

User account management in Informatica involves the following key components:

- **Users.** You can set up different types of user accounts in the Informatica domain. Users can perform tasks based on the roles, privileges, and permissions assigned to them.
- **Authentication.** When a user logs in to an application client, the Service Manager authenticates the user account in the Informatica domain and verifies that the user can use the application client. The Informatica domain can use native or LDAP authentication to authenticate users. The Service Manager organizes user accounts and groups by security domain. It authenticates users based on the security domain the user belongs to.
- **Authentication.** When a user logs in to an application client, the Service Manager authenticates the user account in the Informatica domain and verifies that the user can use the application client.

- **Authentication.** When a user logs in to an application client, the Service Manager authenticates the user account in the Informatica domain and verifies that the user can use the application client.
- **Groups.** You can set up groups of users and assign different roles, privileges, and permissions to each group. The roles, privileges, and permissions assigned to the group determines the tasks that users in the group can perform within the Informatica domain.
- **Privileges and roles.** Privileges determine the actions that users can perform in application clients. A role is a collection of privileges that you can assign to users and groups. You assign roles or privileges to users and groups for the domain and for application services in the domain.
- **Operating system profiles.** If you run the Integration Service on UNIX or Linux, you can configure the Integration Service to use operating system profiles. Use operating system profiles to increase security and to isolate the run-time environment for users. You can create and manage operating system profiles on the Security tab of the Administrator tool.
- **Account lockout.** You can configure account lockout to lock a user account when the user specifies an incorrect login in the Administrator tool or any application clients, like the Developer tool and Analyst tool. You can also unlock a user account.
- **Account lockout.** You can configure account lockout to lock a user account when the user specifies an incorrect login in the Administrator tool or the Developer tool. You can also unlock a user account.
- **Account lockout.** You can configure account lockout to lock a user account when the user specifies an incorrect login in the Administrator tool. You can also unlock a user account.

Default Groups

The Informatica domain has a set of user groups that are created during installation.

By default, the Informatica domain has the following user groups after installation:

- Administrator
- Everyone
- Operator

Administrator Group

The Informatica domain includes a default group named Administrator. The default administrator account created during installation belongs to this group.

The Administrator group has administrator permissions and privileges on the domain and all application services. You can add users to or remove users from the Administrator group. All users in the Administrator group have the same permissions and privileges as the default administrator created during installation.

You cannot delete the default administrator account from the Administrator group and you cannot delete the Administrator group.

Everyone Group

The Informatica domain includes a default group named Everyone. All users in the domain belong to the group.

By default, the Everyone group does not have any privileges. You can assign privileges, roles, and permissions to the Everyone group to grant the same access to all users.

You cannot perform the following tasks on the Everyone group:

- Edit or delete the Everyone group.
- Add users to or remove users from the Everyone group.
- Move a group to the Everyone group.

Operator Group

The Informatica domain includes a default group named Operator.

By default, the Operator group has permission on all of the objects in the domain. You can assign the Operator role to the Operator group and use it to manage the Operator users in the domain.

You can perform the following tasks on the Operator group:

- Assign privileges and roles to the group.
- Add users to or remove users from the group.
- Move a group to the group.
- Edit or delete the group.

Understanding User Accounts

An Informatica domain can have the following types of accounts:

- Default administrator
- Domain administrator
- Application client administrator
- User

An Informatica domain can have the following types of accounts:

- Default administrator
- Domain administrator
- Application client administrator
- User

The Informatica domain has a default administrator account.

Default Administrator

When you install Informatica services, the installer creates the default administrator with a user name and password you provide. You can use the default administrator account to initially log in to the Administrator tool.

The default administrator has administrator permissions and privileges on the domain and all application services.

The default administrator can perform the following tasks:

- Create, configure, and manage all objects in the domain, including nodes, application services, and administrator and user accounts.

- Configure and manage all objects and user accounts created by other domain administrators and application client administrators.
- Log in to any application client.

The default administrator is a user account in the native security domain. You cannot create a default administrator. You cannot disable or modify the user name or privileges of the default administrator. You can change the default administrator password.

Domain Administrator

A domain administrator can create and manage objects in the domain.

The domain administrator can log in to the Administrator tool and create and configure application services in the domain. However, by default, the domain administrator cannot log in to application clients. The default administrator must explicitly give a domain administrator full permissions and privileges to the application services so that they can log in and perform administrative tasks in the application clients.

The domain administrator can log in to the Administrator tool and configure application services in the domain. However, by default, the domain administrator cannot log in to application clients. The default administrator must explicitly give a domain administrator full permissions and privileges to the application services so that they can log in and perform administrative tasks in the application clients.

To create a domain administrator, assign a user the Administrator role for a domain.

Application Client Administrator

An application client administrator can create and manage objects in an application client. You must create administrator accounts for the application clients. To limit administrator privileges and keep application clients secure, create a separate administrator account for each application client.

By default, the application client administrator does not have permissions or privileges on the domain. Without permissions or privileges on the domain, the application client administrator cannot log in to the Administrator tool to manage the application service.

You can set up the following application client administrators:

Informatica Analyst administrator

Has full permissions and privileges in Informatica Analyst. The Informatica Analyst administrator can log in to Informatica Analyst to create and manage projects and objects in projects and perform all tasks in the application client.

To create an Informatica Analyst administrator, assign a user the Administrator role for an Analyst Service and for the associated Model Repository Service.

Informatica Developer administrator

Has full permissions and privileges in Informatica Developer. The Informatica Developer administrator can log in to Informatica Developer to create and manage projects and objects in projects and perform all tasks in the application client.

To create an Informatica Developer administrator, assign a user the Administrator role for a Model Repository Service.

Metadata Manager administrator

Has full permissions and privileges in Metadata Manager. The Metadata Manager administrator can log in to Metadata Manager to create and manage Metadata Manager objects and perform all tasks in the application client.

To create a Metadata Manager administrator, assign a user the Administrator role for a Metadata Manager Service.

Test Data administrator

Has full permissions and privileges in Test Data Manager. The Test Data Manager administrator can log in to Test Data Manager to create and manage Test Data Manager objects and perform all tasks in the application client.

To create a Test Data administrator, assign a user the Administrator role for a Test Data Manager Service.

PowerCenter Client administrator

Has full permissions and privileges on all objects in the PowerCenter Client. The PowerCenter Client administrator can log in to the PowerCenter Client to manage the PowerCenter repository objects and perform all tasks in the PowerCenter Client. The PowerCenter Client administrator can also perform all tasks in the pmrep and pmcmd command line programs.

To create a PowerCenter Client administrator, assign a user the Administrator role for a PowerCenter Repository Service.

User

A user with an account in the Informatica domain can perform tasks in the application clients.

Typically, the default administrator or a domain administrator creates and manages user accounts and assigns roles, permissions, and privileges in the Informatica domain. However, any user with the required domain privileges and permissions can create a user account and assign roles, permissions, and privileges.

Users can perform tasks in application clients based on the privileges and permissions assigned to them.

Managing Users

You can create, edit, and delete users in the native security domain. You cannot delete or modify the properties of user accounts in the LDAP security domains. You cannot modify the user assignments to LDAP groups.

You can create, edit, and delete users depending on the type of PowerCenter Express license. You can assign roles, permissions, and privileges to a user account. The roles, permissions, and privileges assigned to the user determines the tasks the user can perform within the Informatica domain. If you have the PowerCenter Express Personal Edition, you cannot create users or groups. You must use the default Administrator user to perform all tasks.

You can create, edit, and delete users depending on the type of license. You can assign roles, permissions, and privileges to a user account. The roles, permissions, and privileges assigned to the user determines the tasks the user can perform within the Informatica domain.

You can assign roles, permissions, and privileges to a user account in the native security domain or an LDAP security domain. The roles, permissions, and privileges assigned to the user determines the tasks the user can perform within the Informatica domain.

You can also unlock a user account.

Creating Native UsersCreating UsersCreating Users

Add, edit, or delete native users on the Security tab.

1. In the Administrator tool, click the Security tab.
2. On the Security Actions menu, click Create User.
3. Enter the following details for the user:

Property	Description
Login Name	Login name for the user account. The login name for a user account must be unique within the security domain to which it belongs. The name is not case sensitive and cannot exceed 128 characters. It cannot include a tab, newline character, or the following special characters: , + " \ < > ; / * % ? & The name can include an ASCII space character except for the first and last character. All other space characters are not allowed.
Password	Password for the user account. The password can be from 1 through 80 characters long.
Confirm Password	Enter the password again to confirm. You must retype the password. Do not copy and paste the password.
Full Name	Full name for the user account. The full name cannot include the following special characters: < > "
Description	Description of the user account. The description cannot exceed 765 characters or include the following special characters: < > "
Email	Email address for the user. The email address cannot include the following special characters: < > " Enter the email address in the format UserName@Domain.
Phone	Telephone number for the user. The telephone number cannot include the following special characters: < > "

4. Click OK to save the user account.

After you create a user account, the details panel displays the properties of the user account and the groups that the user is assigned to.

Editing General Properties of Native Users

You cannot change the login name of a native user. You can change the password and other details for a native user account.

1. In the Administrator tool, click the Security tab.
2. In the Users section of the Navigator, select a native user account and click Edit.
3. To change the password, select Change Password.

The Security tab clears the Password and Confirm Password fields.

4. Enter a new password and confirm.
5. Modify the full name, description, email, and phone as necessary.
6. Click OK to save the changes.

Assigning Native Users to Native Groups

Assign native users to native groups on the Security tab.

1. In the Administrator tool, click the Security tab.
2. In the Users section of the Navigator, select a native user account and click **Edit**.
3. Click the Groups tab.
4. To assign a native user to a group, select a group name in the All Groups column and click **Add**.
If nested groups do not display in the All Groups column, expand each group to show all nested groups.
You can assign a native user to more than one group. Use the Ctrl or Shift keys to select multiple groups at the same time.
5. To remove a native user from a group, select a group in the Assigned Groups column and click **Remove**.
6. Click **OK** to save the group assignments.

Assigning LDAP Users to Native Groups

You can assign LDAP user accounts to native groups. You cannot change the assignment of LDAP user accounts to LDAP groups.

1. In the Administrator tool, click the Security tab.
2. In the Groups section of the Navigator, select a Native group and click Edit.
3. Click the Users tab.
4. To assign an LDAP user to a group, select an LDAP user in the All Users column and click Add.
5. To remove an LDAP user from a group, select an LDAP user in the Assigned Users column and click Remove.
6. Click OK to save the user assignments.

Enabling and Disabling User Accounts

Users with active accounts can log in to application clients and perform tasks based on their permissions and privileges. If you do not want users to access application clients temporarily, you can disable their accounts. You can enable or disable user accounts in the native or an LDAP security domain. When you disable a user account, the user cannot log in to the application clients.

Users with active accounts can log in to application clients and perform tasks based on their permissions and privileges. If you do not want users to access application clients temporarily, you can disable their accounts. When you disable a user account, the user cannot log in to the application clients.

To disable a user account, select a user account in the Users section of the Navigator and click Disable. When you select a disabled user account, the Security tab displays a message that the user account is disabled. When a user account is disabled, the Enable button is available. To enable the user account, click Enable.

You cannot disable the default administrator account.

Note: When the Service Manager imports a user account from the LDAP directory service, it does not import the LDAP attribute that indicates that a user account is enabled or disabled. The Service Manager imports all user accounts as enabled user accounts. You must disable an LDAP user account in the Administrator tool if you do not want the user to access application clients. During subsequent synchronization with the LDAP server, the user account retains the enabled or disabled status set in the Administrator tool.

Deleting Native Users

To delete a native user account, right-click the user account name in the Users section of the Navigator and select Delete User. Confirm that you want to delete the user account.

You cannot delete the default administrator account. When you log in to the Administrator tool, you cannot delete your user account.

Deleting Users of PowerCenter

When you delete a user who owns objects in the PowerCenter repository, you remove any ownership that the user has over folders, connection objects, deployment groups, labels, or queries. After you delete a user, the default administrator becomes the owner of all objects owned by the deleted user.

When you view the history of a versioned object previously owned by a deleted user, the name of the deleted user appears prefixed by the word "deleted."

Deleting Users of Metadata Manager

When you delete a user who owns shortcuts and folders, Metadata Manager moves the user's personal folder to a folder named Deleted Users owned by the default administrator. The deleted user's personal folder contains all shortcuts and folders created by the user. Any shared folders remain shared after you delete the user.

If the Deleted Users folder contains a folder with the same user name, Metadata Manager names the additional folder "Copy (n) of <username>."

LDAP Users

You cannot add, edit, or delete LDAP users in the Administrator tool. You must manage the LDAP user accounts in the LDAP directory service.

Unlocking a User Account

The domain administrator can unlock a user account that is locked out of the domain. If the user is a native user, the administrator can request that the user reset their password before logging back into the domain.

The user must have a valid email address configured in the domain to receive notifications when their account password has been reset.

If the user is locked out of the LDAP authentication server, the LDAP administrator must unlock the user account in the LDAP server.

1. In the Administrator tool, click the **Security** tab.
2. Click **Account Management**.

The Account Management page displays the following lists of locked-out users:

Locked Out Native Users

Includes user accounts in the Native security domain that are locked out.

Locked Out LDAP Users

Includes user accounts in LDAP security domains that are locked out.

3. Select the users that you want to unlock.
4. Select **Unlock user and reset password** to generate a new password for the user after you unlock the account.
The user receives the new password in an email.
5. Click the **Unlock selected users** button.

Increasing System Memory for Many Users

Processing time for an Informatica domain restart, LDAP user synchronization, and some infacmd and infasetup commands increases proportionally with the number of users in the Informatica domain.

The number of users affects the processing time of the following commands:

- infasetup BackupDomain, DeleteDomain, and RestoreDomain
- infacmd isp ExportDomainObjects, ExportUsersandGroups, ImportDomainObjects, and ImportUsersandGroups
- infacmd oie ExportObjects and ImportObjects

You may need to increase the system memory used by Informatica Services, infasetup, and infacmd when you have a large number of users in the domain. To increase the maximum heap size, configure the following environment variables and specify the value in megabytes:

- INFA_JAVA_OPTS. Determines the maximum heap size used by Informatica Services. Configure on each node where Informatica Services is installed.
- ICMD_JAVA_OPTS. Determines the maximum heap size used by infacmd. Configure on each machine where you run infacmd.
- INFA_JAVA_CMD_OPTS. Determines the maximum heap size used by infasetup. Configure on each machine where you run infasetup.

For example, to configure 2048 MB of system memory on UNIX for the INFA_JAVA_OPTS environment variable, use the following command:

```
setenv INFA_JAVA_OPTS "-Xmx2048m"
```

On Windows, configure the variables as system variables.

The following table lists the minimum requirement for the maximum heap size settings, based on the number of users and services in the domain:

Number of Domain Users	Maximum Heap Size (1-5 Services)	Maximum Heap Size (6-10 Services)
1,000 or less	512 MB (default)	1024 MB
5,000	2048 MB	3072 MB
10,000	3072 MB	5120 MB

Number of Domain Users	Maximum Heap Size (1-5 Services)	Maximum Heap Size (6-10 Services)
20,000	5120 MB	6144 MB
30,000	5120 MB	6144 MB

Note: The maximum heap size settings in the table are based on the number of application services in the domain.

After you configure these environment variables, restart the node for the changes to take effect.

Viewing User Activity

Use the `infacmd isp getUserActivityLog` command or the Logs tab of the Administrator tool to view user activity logs. View user activity log events to determine when a user created, updated, or removed services, nodes, users groups, or roles.

Run the following command to view the user activity log events for all users:

```
infacmd isp getUserActivityLog -dn domain_name -un user_name -pd password
```

The command requires the Administrator role or membership in the Administrator group.

You can view log events based on the following optional filters:

- User name
- Security domain
- Date and time
- Chronological order
- Activity code
- Activity text

You can display the log events on the command line or write it to a file in one the following formats:

- Binary
- Text
- XML

If you print a log in binary format, you can use the `infacmd isp convertUserActivityLog` command to convert it to text or XML format.

For more information about user activity logs and the Logs tab of the Administrator tool, see the *Informatica Administrator Guide*.

User Activity Log Filters

Use one or more filters to retrieve log events for specific users, dates, or events.

Use one or more of the following parameters for the `infacmd isp getUserActivityLog` command to filter log events:

Users and security domains

Optional. The list of users that you want to get log events for. Separate multiple users with a space. Use the wildcard symbol (*) to view logs for multiple users on a single security domain or all security domains. For example, the following strings are valid values for the option:

```
user:Native
"user:*"
"user*"
"*_users_*"
"*:Native"
```

Add the following parameter to the `getUserActivityLog` command to filter log events based on user or security domain:

```
-usrs <UserName>:<SecurityDomain>
```

For example, add the following parameter to retrieve user activity for a user named User1 on all security domains:

```
-usrs "User1:*
```

Date and time

Optional. The range of dates you want to view log events for.

If you enter an end date that is before the start date, the command returns no log events.

Enter the date and time in one of the following formats:

- MM/dd/yyyy
- MM/dd/yyyy HH:mm:ss
- yyyy-MM-dd
- yyyy-MM-dd HH:mm:ss

Add the following parameter to the `getUserActivityLog` command to filter the log by start date or end date:

```
-sd <start_date> -ed <end_date>
```

For example, add the following parameter to retrieve user activity between January 1, 2014 and February 3, 2014:

```
-sd 01/01/2014 -ed 02/03/2014
```

Activity code

Optional. Returns log events based on the activity code.

Use the wildcard symbol (*) to retrieve log events for multiple activity codes. Valid activity codes include:

- CCM_10437. Indicates that an activity succeeded.
- CCM_10438. Indicates that an activity failed.

Add the following parameter to the `getUserActivityLog` command to filter by activity code:

```
-ac <activity_code>
```

For example, add the following parameter to retrieve log events that succeeded:

```
-ac CCM_10437
```

If you use the wildcard symbol, enclose the argument in quotation marks.

Activity text

Optional. Returns log events based on a string found in the activity text.

Add the following parameter to the `getUserActivityLog` command to filter by activity text:

```
-atxt <activity_text>
```

Use the wildcard symbol (*) to retrieve logs for multiple events. For example, the following parameter returns all log events that contain the phrase "Enabling service" in their description:

```
-atxt "**Enabling service**"
```

If you use the wildcard symbol, enclose the argument in quotation marks.

Chronological order

Optional. Prints log events in reverse chronological order. If you do not specify this parameter, the command displays log events in chronological order.

Add the following parameter to the `getUserActivityLog` command to print the most recent event first:

```
-ro true
```

Writing and Viewing User Activity Log Events

You can write user activity log events to a file or display it in the command line when you use the `infacmd isp` `getUserActivityLog` command. Write the user activity log events to the format based on how you plan to use the exported log events file.

Writing and Viewing Log Files

To write the user activity log events to a file, run the command with the output file parameter `-lo`:

```
-lo output_file_name
```

If you do not specify an output format, the command writes the log events to a text file. For example, run the following command to write log events to a file named `log.txt`:

```
infacmd isp getUserActivityLog -dn TestDomain -un Administrator -pd Administrator -lo  
log.txt
```

To specify an output format, run the command with the format parameter `-fm`:

```
-fm output_format_BIN_TEXT_XML
```

Valid formats include:

- Bin (binary). Use binary format to back up the log events in binary format. You might need to use this format to send log events to Informatica Global Customer Support
- Text. Use text format if you want to analyze the log events in a text editor.
- XML. Use XML format if you want to analyze log events in an external tool that uses XML or if you want to use XML tools, such as XSLT.

If you specify text or XML as the output format, but you do not specify an output file, the command displays the text or XML log on the command line.

If you specify binary as the output format, you must provide an output file name.

For example, run the following command to print log events to a file named `log.xml`:

```
infacmd isp getUserActivityLog -dn TestDomain -un Administrator -pd Administrator -fm  
xml -lo log.xml
```

Converting Log Files

If you use the `getUserActivity` command to write log events to a binary file, you can convert the file to text or XML format.

Run the following command to convert a binary log you retrieved to text or XML format:

```
infacmd isp convertUserActivityLogFile -in BIN_input_file_name -fm  
output_format_TEXT_XML -lo output_file_name
```

For example, run the following command to convert a binary input file named `log.bin` to XML format and output it to a file named `convertedLog.xml`:

```
infacmd isp convertUserActivityLogFile -in log.bin -fm XML -lo convertedLog.xml
```

To display the log on the command line, omit the output file name.

If you omit the format, the command uses the text format.

Managing Groups

You can create, edit, and delete groups in the native security domain.

You can assign roles, permissions, and privileges to a group in the native or an LDAP security domain. You cannot delete or modify the properties of group accounts in the LDAP security domains. The roles, permissions, and privileges assigned to the group determines the tasks that users in the group can perform within the Informatica domain.

You can assign roles, permissions, and privileges to a group. The roles, permissions, and privileges assigned to the group determines the tasks that users in the group can perform within the Informatica domain.

You can assign roles, permissions, and privileges to a group. The roles, permissions, and privileges assigned to the group determines the tasks that users in the group can perform within the Informatica domain.

Adding a Native Group

Add, edit, or remove native groups on the Security tab.

A native group can contain native or LDAP user accounts or other native groups. You can create multiple levels of native groups. For example, the Finance group contains the AccountsPayable group which contains the OfficeSupplies group. The Finance group is the parent group of the AccountsPayable group and the AccountsPayable group is the parent group of the OfficeSupplies group. Each group can contain other native groups.

A native group can contain user accounts or other native groups. You can create multiple levels of native groups. For example, the Finance group contains the AccountsPayable group which contains the OfficeSupplies group. The Finance group is the parent group of the AccountsPayable group and the AccountsPayable group is the parent group of the OfficeSupplies group. Each group can contain other native groups.

A native group can contain user accounts or other native groups. You can create multiple levels of native groups. For example, the Finance group contains the AccountsPayable group which contains the OfficeSupplies group. The Finance group is the parent group of the AccountsPayable group and the AccountsPayable group is the parent group of the OfficeSupplies group. Each group can contain other native groups.

1. In the Administrator tool, click the Security tab.
2. On the Security Actions menu, click Create Group.

3. Enter the following information for the group:

Property	Description
Name	Name of the group. The name is not case sensitive and cannot exceed 128 characters. It cannot include a tab, newline character, or the following special characters: , + " \ < > ; / * % ? The name can include an ASCII space character except for the first and last character. All other space characters are not allowed.
Parent Group	Group to which the new group belongs. If you select a native group before you click Create Group, the selected group is the parent group. Otherwise, Parent Group field displays Native indicating that the new group does not belong to a group.
Description	Description of the group. The group description cannot exceed 765 characters or include the following special characters: < > "

4. Click Browse to select a different parent group.
You can create more than one level of groups and subgroups.
5. Click OK to save the group.

Editing Properties of a Native Group

After you create a group, you can change the description of the group and the list of users in the group. You cannot change the name of the group or the parent of the group. To change the parent of the group, you must move the group to another group.

1. In the Administrator tool, click the Security tab.
2. In the Groups section of the Navigator, select a native group and click Edit.
3. Change the description of the group.
4. To change the list of users in the group, click the Users tab.
The Users tab displays the list of users in the domain and the list of users assigned to the group.
5. To assign users to the group, select a user account in the All Users column and click Add.
6. To remove a user from a group, select a user account in the Assigned Users column and click Remove.
7. Click OK to save the changes.

Moving a Native Group to Another Native Group

To organize the groups of users in the native security domain, you can set up nested groups and move a group to another group.

To move a native group to another native group, right-click the name of a native group in the Groups section of the Navigator and select Move Group.

Deleting a Native Group

To delete a native group, right-click the group name in the Groups section of the Navigator and select Delete Group.

When you delete a group, the users in the group lose their membership in the group and all permissions or privileges inherited from group.

When you delete a group, the Service Manager deletes all groups and subgroups that belong to the group.

LDAP Groups

You cannot add, edit, or delete LDAP groups or modify user assignments to LDAP groups in the Administrator tool. You must manage groups and user assignments in the LDAP directory service.

Managing Operating System Profiles

Create and manage operating system profiles on the Security tab of the Administrator tool or from the command line. You can create, edit, and delete operating system profiles. You can assign or change the default operating system profile to users and groups.

If the Data Integration Service is configured to use operating system profiles, it runs mappings, profiles, and workflows with the operating system profile. If the PowerCenter Integration Service is configured to use operating system profiles, it runs workflows with the operating system profile.

Create, edit, and delete operating system profiles in the **Operating System Profiles** view of the **Security** tab.

Complete the following steps to create an operating system profile:

1. Enter an operating system profile name and a system user name.
2. Select the Integration Services and configure the operating system profile properties.
3. Optionally, assign permissions on the operating system profile.

You can assign users and groups to operating system profiles and assign a default profile to users and groups after you create an operating system profile.

Operating System Profile Properties for the PowerCenter Integration Service

Service process variables that are set in session properties and parameter files override the operating system profile settings.

The following table describes the operating system profile properties for the PowerCenter Integration Service:

Property	Description
Name	Read-only name of the operating system profile. The name cannot exceed 128 characters. It cannot include spaces or the following special characters: \ / : * ? " < > [] = + ; ,
System User Name	Read-only name of an operating system user that exists on the machines where the PowerCenter Integration Service runs. The PowerCenter Integration Service runs workflows using the system access of the system user defined for the operating system profile.
\$PMRootDir	Root directory accessible by the node. This is the root directory for other service process variables. It cannot include the following special characters: * ? < > " ,

Property	Description
\$PMSessionLogDir	Directory for session logs. It cannot include the following special characters: * ? < > " , Default is \$PMRootDir/SessLogs.
\$PMBadFileDir	Directory for reject files. It cannot include the following special characters: * ? < > " , Default is \$PMRootDir/BadFiles.
\$PMCacheDir	Directory for index and data cache files. You can increase performance when the cache directory is a drive local to the PowerCenter Integration Service process. Do not use a mapped or mounted drive for cache files. It cannot include the following special characters: * ? < > " , Default is \$PMRootDir/Cache.
\$PMTargetFileDir	Directory for target files. It cannot include the following special characters: * ? < > " , Default is \$PMRootDir/TgtFiles.
\$PMSourceFileDir	Directory for source files. It cannot include the following special characters: * ? < > " , Default is \$PMRootDir/SrcFiles.
\$PmExtProcDir	Directory for external procedures. It cannot include the following special characters: * ? < > " , Default is \$PMRootDir/ExtProc.
\$PMTempDir	Directory for temporary files. It cannot include the following special characters: * ? < > " , Default is \$PMRootDir/Temp.
\$PMLookupFileDir	Directory for lookup files. It cannot include the following special characters: * ? < > " , Default is \$PMRootDir/LkpFiles.
\$PMStorageDir	Directory for run-time files. Workflow recovery files save to the \$PMStorageDir configured in the PowerCenter Integration Service properties. Session recovery files save to the \$PMStorageDir configured in the operating system profile. It cannot include the following special characters: * ? < > " , Default is \$PMRootDir/Storage.
Environment Variables	Name and value of environment variables used by the Integration Service at run time. If you specify the LD_LIBRARY_PATH environment variable in the operating system profile properties, the Integration Service appends the value of this variable to its LD_LIBRARY_PATH environment variable. The Integration Service uses the value of its LD_LIBRARY_PATH environment variable to set the environment variables of the child processes generated for the operating system profile. If you do not specify the LD_LIBRARY_PATH environment variable in the operating system profile properties, the Integration Service uses its LD_LIBRARY_PATH environment variable.

Operating System Profile Properties for the Data Integration Service

The following table describes the operating system profile properties for the Data Integration Service:

Property	Description
Name	Read-only name of the operating system profile. The name cannot exceed 128 characters. It cannot include spaces or the following special characters: \ / : * ? " < > [] = + ; ,
System User Name	Read-only name of an operating system user that exists on the systems where the Data Integration Service runs. The Data Integration Service runs mappings, workflows, and profiling jobs using the system access of the operating system user.
\$DISRootDir	Root directory accessible by the node. This is the root directory for other service process variables. It cannot include the following special characters: * ? < > " , []
\$DISTempDir	Directory for temporary files created when jobs are run. It cannot include the following special characters: * ? < > " , [] Default is <root directory>/disTemp.
\$DISCachedir	Directory for index and data cache files for transformations. It cannot include the following special characters: * ? < > " , [] Default is <root directory>/cache.
\$DISSourceDir	Directory for source flat files used in a mapping. It cannot include the following special characters: * ? < > " , [] Default is <root directory>/source.
\$DISTargetDir	Directory for target flat files used in a mapping. It cannot include the following special characters: * ? < > " , [] Default is <root directory>/target.
\$DISRejectedFilesDir	Directory for reject files. Reject files contain rows that were rejected when running a mapping. It cannot include the following special characters: * ? < > " , [] Default is <root directory>/reject.
\$DISLogDir	Directory for logs. It cannot include the following special characters: * ? < > " , [] Default is <root directory>/disLogs.
Enable Hadoop Impersonation Properties	Indicates that the Data Integration Service uses the Hadoop impersonation user to run mappings, workflows, and profiling jobs in a Hadoop environment. Default Hadoop impersonation user is the logged in user. To specify a different Hadoop impersonation user, select Use the Specified User as Hadoop Impersonation User and enter a user name.

Property	Description
Environment Variables	<p>Name and value of environment variables used by the Integration Service at run time.</p> <p>If you specify the LD_LIBRARY_PATH environment variable in the operating system profile properties, the Integration Service appends the value of this variable to its LD_LIBRARY_PATH environment variable. The Integration Service uses the value of its LD_LIBRARY_PATH environment variable to set the environment variables of the child processes generated for the operating system profile.</p> <p>If you do not specify the LD_LIBRARY_PATH environment variable in the operating system profile properties, the Integration Service uses its LD_LIBRARY_PATH environment variable.</p> <p>Note: On AIX, you must set the LD_LIBRARY_PATH environment variable to INFA_HOME/services/shared/bin for the Data Integration Service to successfully run mappings, profiles, and workflows with operating system profiles.</p>
Flat File Cache Directory	<p>Directory of the flat file cache where the Analyst tool stores uploaded flat files.</p> <p>If the Analyst Service connects to a Data Integration Service that uses operating system profiles, the operating system user specified in the operating system profile must have access to this flat file cache directory. When you import a reference table or flat file source, the Analyst tool uses the files from this directory to create a reference table or flat file data object. Restart the Analyst Service if you change the flat file location.</p>

Creating an Operating System Profile

Create an operating system profile and assign it to users and groups to increase security and to isolate the run-time user environment. You can create one or more operating system profiles. The PowerCenter Integration Service uses the operating system profile to run workflows. The Data Integration Service uses the operating system profile to run mappings, profiles, and workflows.

1. In the Administrator tool, click the **Security** tab.
2. On the Security Actions menu, click **Create Operating System Profile**.
The **Create Operating System Profile - Step 1 of 3** dialog box appears.
3. Enter the following general properties for the operating system profile:

Property	Description
Name	<p>Name of the operating system profile. The name is not case sensitive and must be unique within the domain. It cannot exceed 128 characters or begin with @. It also cannot contain the following special characters:</p> <p>% * + \ / ? ; < ></p> <p>The name can contain an ASCII space character except for the first and last character. All other space characters are not allowed.</p>
System User Name	<p>Name of an operating system user that exists on the machines where the Integration Service runs. The Integration Service runs workflows or jobs using the system access of the system user defined for the operating system profile.</p> <p>Note: When you create operating system profiles, you cannot specify the system user name as root or use a non-root user with uid==0.</p>

4. Click **Next**.
The **Configure Operating System Profile - Step 2 of 3** dialog box appears.
5. Select one or both of the Integration Services that will use the operating system profile.

- PowerCenter Integration Service
 - Data Integration Service
6. Configure the operating system profile properties for the Integration Services.
 7. If the Data Integration Service runs mappings, profiles, and workflows in a Hadoop environment, configure the Hadoop impersonation properties as follows:
 - a. Select **Enable Hadoop Impersonation Properties**.
 - b. Choose to use the logged in user or specify a Hadoop impersonation user to run Hadoop jobs.
 8. Optionally, configure the environment variables.
 9. If the Analyst Service connects to a Data Integration Service that uses operating system profiles, configure the Analyst Service properties.
 10. Click **Next**.
The **Assign Groups and Users to Operating System Profile - Step 3 of 3** dialog box appears.
 11. In the **Groups** tab, assign groups to the operating system profile as follows:
 - a. To assign specific groups to the operating system profile, select one or more groups and click **Add**.
 - b. To assign all available groups to the operating system profile, click **Add All**.
 12. Optionally, assign the operating system profile as the default profile to one or more groups. To assign a default profile, select **Default Profile** for the group in the Selected Group(s) list.
 13. In the **Users** tab, assign users to the operating system profile as follows:
 - a. To assign specific users to the operating system profile, select one or more users and click **Add**.
 - b. To assign all available users to the operating system profile, click **Add All**.
 14. Optionally, assign the operating system profile as the default profile to one or more users. To assign a default profile, select **Default Profile** for the user in the Selected User(s) list.
 15. Click **Finish**.
After you create the operating system profile, the details panel displays the properties of the operating system profile and the groups and users that the profile is assigned to.

Editing an Operating System Profile

You can edit an operating system profile to change the operating system profile properties.

You cannot edit the name or the system user name after you create an operating system profile. If you do not want to use the operating system user specified in the operating system profile, delete the operating system profile.

1. In the Administrator tool, click the **Security** tab.
2. Select the **Operating System Profiles** view.
3. Select the operating system profile.
4. In the **Properties** tab, click **Edit**.
The **Edit Properties** dialog box appears.
5. Select the **Data Integration Service** or the **PowerCenter Integration Service** that you want to configure.
6. Edit the Integration Service properties.
7. Click **OK**.

Assigning a Default Operating System Profile to a User or Group

When a user or group has access to more than one operating system profile, assign a default operating system profile that the Integration Service uses to run jobs and workflows. You can assign any operating system profile with direct permission as the default profile to a user or group. A user or group can have only one default operating system profile. However, you can assign the same operating system profile as the default profile to more than one user or group.

1. On the Security tab, select the **Users or Groups** view.
2. In the Navigator, select the user or group.
3. In the content panel, select the **Permissions** view.
4. Click the **Operating System Profiles** tab.
5. Click the **Assign or Change the Default Operating System Profile** button.

The **Assign or Change the Default Operating System Profile** dialog box appears.

6. Select a profile from the **Default Operating System Profile** list. Or, select **Do not assign a default operating system profile** from the list to remove the default profile that is assigned to a user or group.
7. Click **OK**.

In the details panel, the **Default Profile** column displays **Yes (Direct)** for the operating system profile.

Deleting an Operating System Profile

To delete an operating system profile, right-click the operating system profile name in the Operating System Profile section of the Navigator and select **Delete Profile**.

After you delete an operating system profile, assign another operating system profile to the users and groups that the operating system profile was assigned to as the default profile. If the PowerCenter Integration Service uses operating system profiles, assign another operating system profile to the repository folders and workflows that the operating system profile was assigned to.

Working with Operating System Profiles in a Secure Domain

You can use operating system profiles in an Informatica domain that has secure communication enabled.

Consider the following rules and guidelines when you use operating system profiles in a domain that has secure communication enabled:

- You must set the following environment variable for the operating system profile:

INFA_TRUSTSTORE

Set the value to the directory that contains the truststore files for the SSL certificates for the secure domain. The directory must contain a truststore file named `infa_truststore.pem`.

INFA_TRUSTSTORE_PASSWORD

If you use a custom truststore, set the value to the password for the `infa_truststore.pem` that contains the SSL certificate for the secure domain. The password must be encrypted. Use the command line program `pmpasswd` to encrypt the password.

- Additionally, if the PowerCenter Integration Service uses the Session on Grid option, you must set the following environment variable for the operating system profile:

INFA_KEYSTORE

Set the value to the directory that contains the keystore files for the SSL certificates for the secure domain. The directory must contain a keystore file named `infa_keystore.pem`.

You can set the environment variables for the operating system profile in the Administrator tool. To set the environment variables for the operating system profile, click **Security > Operating System Profiles**. Edit the properties of the operating system profile and set the environment variables.

Working with Operating System Profiles in a Domain with Kerberos Authentication

You can use operating system profiles in an Informatica domain that runs on a network with Kerberos authentication.

Consider the following rules and guidelines when you use operating system profiles in a domain that runs on a network with Kerberos authentication:

- The user account for the operating system profile must be a principal in the Active Directory service used for Kerberos authentication and imported into an LDAP security domain in the Informatica domain.
- The user account must have a Kerberos credentials cache file that is accessible to the operating system profile user account. Each operating system profile user account must have a separate credentials cache file.
- The credentials cache file for the operating system profile user account must be forwardable. For example, if you use the *kinit* utility to create the credentials cache file, you must include the *-f* option.
- The credentials cache file for the operating system profile user account must be available when you run a workflow that uses an operating system profile.
- The credentials cache file for the operating system profile user account must always have the latest credentials. You can run a job scheduler utility, such as *cron*, to regularly update the user credentials in the credentials cache file.
- You must set the following environment variables for the operating system profile:

INFA_OSPI_SECURITY_DOMAIN

Set the value to the name of the security domain that contains the user account for the operating system profile. If the user account is in the user realm security domain for Kerberos, you do not need to set this variable. The user realm security domain for Kerberos is the security domain created during installation which has the same name as the Kerberos user realm.

KRB5_CONFIG

Set the value to the path and file name of the Kerberos configuration file. The name of the Kerberos configuration file is *krb5.conf*.

KRB5CCNAME

Set the value to the path and file name of the Kerberos credentials cache file for the operating system profile user account.

You can set the environment variables for the operating system profile in the Administrator tool. To set the environment variables for the operating system profile, click **Security > Operating System Profiles**. Edit the properties of the operating system profile and set the environment variables.

Account Lockout

To improve security in the Informatica domain, an administrator can enforce lockout of domain user accounts, including other administrator users, after multiple failed logins.

The administrator can specify the number of failed login attempts a user can make before the user account is locked. If an account is locked out, the administrator can unlock the account in the Informatica domain.

When the administrator unlocks a user account, the administrator can select the "Unlock user and reset password" option to reset the user password. The administrator can send an email to the user to request that the user change the password before logging back into the domain. To enable the domain to send emails to users when their passwords are reset, configure the email server settings for the domain.

If the user is locked out of the Informatica domain and the LDAP server, the Informatica administrator can unlock the user account in the Informatica domain. The user cannot log in to the Informatica domain until the LDAP administrator also unlocks the user account in the LDAP server.

Note: If the Informatica domain uses Kerberos network authentication, you cannot configure lockout for user accounts. The **Account Management** view is not available in the **Security** tab of the Administrator tool.

Configuring Account Lockout

Select the account lockout options to lock out user accounts in the Informatica domain after multiple failed logins.

1. In the Administrator tool, click **Security > Account Management**.
2. In **Account Lockout Configuration** section, click **Edit**.
3. Set the following properties:

Property	Description
Enable Account Lockout	Enforces lockout of an Informatica domain user account after a specified number of failed logins. By default, this option does not enforce lockout of administrator user accounts. You must select the Enable Admin Account Lockout option to enforce lockout for administrator user accounts.
Enable Admin Account Lockout	Enforces lockout of an Informatica domain administrator user account after a specified number of failed logins. You must select the Enable Account Lockout option before you can enforce lockout for administrator user accounts.
Maximum Login Attempts	Specifies the maximum number of consecutive login failures allowed before a user account is locked out of the Informatica domain.

Rules and Guidelines for Account Lockout

Consider the following rules and guidelines when you enforce account lockout for Informatica users:

- If an application service runs under a user account and the wrong password is provided for the application service, the user account can become locked when the application service tries to start. The Data Integration Service, Web Services Hub Service, and PowerCenter Integration Service are resilient application services that use a user name and password to authenticate with the Model Repository Service or PowerCenter Repository Service. If the Data Integration Service, Web Services Hub Service, or PowerCenter Integration Service continually try to restart after a failed login, the domain eventually locks the associated user account.

- If an LDAP user account is locked out of the Informatica domain and the LDAP authentication server, the Informatica domain administrator can unlock the account in the Informatica domain. The LDAP administrator can unlock the user account in the LDAP server.
- If you enable account lockout in the Informatica domain and in the LDAP server, configure the same threshold for login failures in the Informatica domain and in the LDAP server to avoid confusion about the account lockout policy.
- If account lockout is not enabled in the Informatica domain but a user is locked out, verify that the user is not locked out in the LDAP server.

CHAPTER 9

Privileges and Roles

This chapter includes the following topics:

- [Privileges and Roles Overview, 135](#)
- [Domain Privileges, 137](#)
- [Analyst Service Privileges, 146](#)
- [Content Management Service Privileges, 147](#)
- [Data Integration Service Privileges, 147](#)
- [Metadata Manager Service Privileges, 148](#)
- [Model Repository Service Privileges, 151](#)
- [PowerCenter Repository Service Privileges, 153](#)
- [PowerExchange Listener Service Privileges, 166](#)
- [PowerExchange Logger Service Privileges, 167](#)
- [Scheduler Service Privileges, 168](#)
- [Test Data Manager Service Privileges, 168](#)
- [Managing Roles, 176](#)
- [Assigning Privileges and Roles to Users and Groups, 180](#)
- [Viewing Users with Privileges for a Service, 182](#)
- [Troubleshooting Privileges and Roles, 182](#)

Privileges and Roles Overview

You manage user security with privileges and roles.

You can modify privileges and roles depending on the type of PowerCenter Express license.

Privileges

Privileges determine the actions that users can perform in application clients. Informatica includes the following privileges:

- Domain privileges. Determine actions that users can perform on the Informatica domain using the Administrator tool and the infacmd and pmrep command line programs.
- Domain privileges. Determine actions on the Informatica domain that users can perform using the Administrator tool.

- Analyst Service privilege. Determines actions that users can perform using Informatica Analyst.
- Content Management Service privilege. Determines actions that users can perform using reference tables in the Informatica Developer tool and the Informatica Analyst tool.
- Data Integration Service privilege. Determines actions on applications that users can perform using the Administrator tool and the infacmd command line program. This privilege also determines whether users can drill down and export profile results.
- Data Integration Service privilege. Determines actions on applications that users can perform using the Administrator tool. This privilege also determines whether users can drill down and export profile results.
- Metadata Manager Service privileges. Determine actions that users can perform using Metadata Manager.
- Model Repository Service privilege. Determines actions on projects that users can perform using Informatica Analyst and Informatica Developer.
- Model Repository Service privilege. Determines actions on projects that users can perform using Informatica Developer.
- PowerCenter Repository Service privileges. Determine PowerCenter repository actions that users can perform using the Repository Manager, Designer, Workflow Manager, Workflow Monitor, and the pmrep and pmcmd command line programs.
- PowerExchange application service privileges. Determine actions that users can perform on the PowerExchange Listener Service and PowerExchange Logger Service using the infacmd pwx commands.
- Scheduler Service privileges. Determine actions that users can perform using the Scheduler Service.
- Test Data Manager Service privileges. Determine data discovery, data masking, data subset, and test data generation tasks that users can perform using the Test Data Manager.

Privileges determine the actions that users can perform in application clients. Informatica includes domain privileges that determine actions that users can perform using the Administrator tool.

You assign privileges to users and groups for application services. You can assign different privileges to a user for each application service of the same service type.

You assign privileges to users and groups on the **Security tab** of the Administrator tool.

The Administrator tool organizes privileges into levels. A privilege is listed below the privilege that it includes. Some privileges include other privileges. When you assign a privilege to users and groups, the Administrator tool also assigns any included privileges.

Privilege Groups

The domain and application service privileges are organized into privilege groups. A privilege group is an organization of privileges that define common user actions. For example, the domain privileges include the following privilege groups:

- Tools. Includes privileges to log in to the Administrator tool.
- Security Administration. Includes privileges to manage users, groups, roles, and privileges.
- Domain Administration. Includes privileges to manage the domain, folders, nodes, grids, licenses, and application services.
- Domain Administration. Includes privileges to manage the domain, folders, and application services.
- Security Administration. Includes privileges to manage users, groups, roles, and privileges.
- Domain Administration. Includes privileges to manage the domain, folders, nodes, grids, licenses, and application services.
- Tools. Includes privileges to log in to the Administrator tool.
- Monitoring. Includes privileges to monitor Ultra Messaging deployments and view statistics.

Tip: When you assign privileges to users and user groups, you can select a privilege group to assign all privileges in the group.

Roles

A role is a collection of privileges that you assign to a user or group. Each user within an organization has a specific role, whether the user is a developer, administrator, basic user, or advanced user.

For example, the PowerCenter Developer role includes all the PowerCenter Repository Service privileges or actions that a developer performs.

You assign a role to users and groups for the domain and for application services in the domain.

Tip: If you organize users into groups and then assign roles and permissions to the groups, you can simplify user administration tasks. For example, if a user changes positions within the organization, move the user to another group. If a new user joins the organization, add the user to a group. The users inherit the roles and permissions assigned to the group. You do not need to reassign privileges, roles, and permissions. For more information, see the following Informatica How-To Library article:

<https://kb.informatica.com/h2l/HowTo%20Library/1/0236-GroupsAndRolesToManageAccessControl.pdf>.

Tip: If you organize users into groups and then assign roles and permissions to the groups, you can simplify user administration tasks. For example, if a user changes positions within the organization, move the user to another group. If a new user joins the organization, add the user to a group. The users inherit the roles and permissions assigned to the group. You do not need to reassign privileges, roles, and permissions.

Domain Privileges

Domain privileges determine the actions that users can perform using the Administrator tool and the `infacmd` and `pmrep` command line programs.

Domain privileges determine the actions that users can perform using the Administrator tool.

The following table describes each domain privilege group:

Privilege Group	Description
Security Administration	Includes privileges to manage users, groups, roles, and privileges.
Domain Administration	Includes privileges to manage the domain, folders, nodes, grids, licenses, application services, and connections.
Monitoring	Includes privileges to configure monitoring statistics and reports, view monitoring for integration objects, and access monitoring.

Privilege Group	Description
Tools	Includes privileges to log in to the Administrator tool.
Cloud Administration	Includes privileges to add Informatica Cloud organizations in the Administrator tool and view them.

Privilege Group	Description
Security Administration	Includes privileges to manage users, groups, roles, and privileges.
Domain Administration	Includes privileges to manage the domain, application services, and connections.
Monitoring	Includes privileges to configure monitoring statistics and reports, view monitoring for integration objects, and access monitoring.
Tools	Includes privileges to log in to the Administrator tool.

Privilege Group	Description
Security Administration	Includes privileges to manage users, groups, roles, and privileges.
Domain Administration	Includes privileges to manage the domain, application services, and connections.
Monitoring	Includes privileges to monitor UM deployments and view statistics.
Tools	Includes privileges to log in to the Administrator tool.

Security Administration Privilege Group

Privileges in the Security Administration privilege group and domain object permissions determine the security management actions users can perform.

Some security management tasks are determined by the Administrator role, not by privileges or permissions.

Some security management tasks are determined by the Administrator role, not by privileges or permissions. A user assigned the Administrator role for the domain can complete the following tasks:

- Create, edit, and delete operating system profiles.
- Grant permission on operating system profiles.

Note: To complete security management tasks in the Administrator tool, users must also have the Access Informatica Administrator privilege.

Grant Privileges and Roles Privilege

Users assigned the Grant Privileges and Roles privilege can assign privileges and roles to users and groups.

The following table lists the required permissions and the actions that users can perform with the Grant Privileges and Roles privilege:

Permission On	Description
Domain or application service	User is able to perform the following actions: <ul style="list-style-type: none">- Assign privileges and roles to users and groups for the domain or application service.- Edit and remove the privileges and roles assigned to users and groups.

Manage Users, Groups, and Roles Privilege

Users assigned the Manage Users, Groups, and Roles privilege can configure LDAP authentication and manage users, groups, and roles.

The Manage Users, Groups, and Roles privilege includes the Grant Privileges and Roles privilege.

The following table lists the required permissions and the actions that users can perform with the Manage Users, Groups, and Roles privilege:

Permission On	Description
-	User is able to perform the following actions: <ul style="list-style-type: none">- Configure LDAP authentication for the domain.- Create, edit, and delete users, groups, and roles.- Import LDAP users and groups.
Operating system profile	User is able to edit operating system profile properties.

Domain Administration Privilege Group

Domain management actions that users can perform depend on privileges in the Domain Administration group and permissions on domain objects.

Some domain management tasks are determined by the Administrator role, not by privileges or permissions. A user assigned the Administrator role for the domain can complete the following tasks:

- Configure domain properties.
- Grant permission on the domain.
- Manage and purge log events.
- Receive domain alerts.
- Run the License Report.
- View user activity log events.
- Shut down the domain.
- Access the service upgrade wizard.

Users who are assigned domain object permissions but not privileges can complete some domain management tasks. The following table lists the actions that users can perform when they are assigned domain object permissions only:

Permission On	Description
Domain	User can perform the following actions: <ul style="list-style-type: none">- View domain properties and log events.- Configure monitoring settings.
Folder	User can view folder properties.
Application service	User can view application service properties and log events.
License object	User can view license object properties.
Grid	User can view grid properties.
Node	User can view node properties.
Web Services Hub	User can run the Web Services Report.

Note: To complete domain management tasks in the Administrator tool, users must also have the Access Informatica Administrator privilege.

Manage Service Execution Privilege

Users assigned the Manage Service Execution privilege can enable and disable application services and receive application service alerts.

The following table lists the required permissions and the actions that users can perform with the Manage Service Execution privilege:

Permission On	Description
Application service	User is able to perform the following actions: <ul style="list-style-type: none">- Enable and disable application services and service processes. To enable and disable a Metadata Manager Service, users must also have permission on the associated PowerCenter Integration Service and PowerCenter Repository Service.- Receive application service alerts.

Permission On	Description
Application service	User is able to perform the following actions: <ul style="list-style-type: none">- Enable and disable application services and service processes.- Receive application service alerts.

Manage Services Privilege

Users assigned the Manage Services privilege can create, configure, move, remove, and grant permission on application services and license objects.

The Manage Services privilege includes the Manage Service Execution privilege.

The following table lists the required permissions and the actions that users can perform with the Manage Services privilege:

Permission On	Description
Domain or parent folder	User is able to create license objects.
Domain or parent folder, node or grid where application service runs, license object, and any associated application service	User is able to create application services.
Application service	User is able to perform the following actions: <ul style="list-style-type: none"> - Configure application services. - Grant permission on application services.
Original and destination folders	User is able to move application services or license objects from one folder to another.
Domain or parent folder and application service	User is able to remove application services.
Analyst Service	User is able to create and delete audit trail tables.
Metadata Manager Service	User is able to perform the following actions: <ul style="list-style-type: none"> - Back up Metadata Manager repository content. - Delete Metadata Manager repository content. - Upgrade the content of the Metadata Manager Service. <p>Note: To create or restore Metadata Manager repository content, the user must belong to the default Administrator group.</p>
Metadata Manager Service PowerCenter Repository Service	User is able to restore the PowerCenter repository for Metadata Manager.
Model Repository Service	User is able to perform the following actions: <ul style="list-style-type: none"> - Create and delete Model repository content. - Create, delete, and re-index the search index. - Upgrade the content of the Model Repository Service from the Actions menu or from the command line. The user must also have the Create, Edit and Delete Projects privilege on the Model Repository Service and write permission on the projects.
PowerCenter Integration Service	User is able to run the PowerCenter Integration Service in safe mode.

Permission On	Description
PowerCenter Repository Service	<p>User is able to perform the following actions:</p> <ul style="list-style-type: none"> - Back up, restore, and upgrade the PowerCenter repository. - Configure data lineage for the PowerCenter repository. - Copy content from another PowerCenter repository. - Close user connections and release PowerCenter repository locks. - Create and delete PowerCenter repository content. - Create, edit, and delete reusable metadata extensions in the PowerCenter Repository Manager. - Enable version control for the PowerCenter repository. - Manage a PowerCenter repository domain. - Perform an advanced purge of object versions at the repository level in the PowerCenter Repository Manager. - Register and unregister PowerCenter repository plug-ins. - Run the PowerCenter repository in exclusive mode. - Send PowerCenter repository notifications to users. - Update PowerCenter repository statistics. - Upgrade the content of the PowerCenter Repository Service.
Test Data Manager Service	<p>User is able to perform the following actions:</p> <ul style="list-style-type: none"> - Create and delete the Test Data Manager repository content. - Upgrade the content of the Test Data Manager Service.
License object	<p>User is able to perform the following actions:</p> <ul style="list-style-type: none"> - Edit license objects. - Grant permission on license objects.
License object and application service	User is able to assign a license to an application service.
Domain or parent folder and license object	User is able to remove license objects.

Permission On	Description
Domain where application service runs, and any associated application service	User is able to create application services.
Application service	<p>User is able to perform the following actions:</p> <ul style="list-style-type: none"> - Configure application services. - Grant permission on application services.
Model Repository Service	<p>User is able to perform the following actions:</p> <ul style="list-style-type: none"> - Create and delete Model repository content. - Create, delete, and re-index the search index.

Manage Nodes and Grids Privilege

Users assigned the Manage Nodes and Grids privilege can create, configure, move, remove, shut down, and grant permission on nodes and grids.

The following table lists the required permissions and the actions that users can perform with the Manage Nodes and Grids privilege:

Permission On	Description
Domain or parent folder	User is able to create nodes.
Domain or parent folder and nodes assigned to the grid	User is able to create grids.
Node or grid	User is able to perform the following actions: <ul style="list-style-type: none">- Configure and shut down nodes and grids.- Grant permission on nodes and grids.
Original and destination folders	User is able to move nodes and grids from one folder to another.
Domain or parent folder and node or grid	User is able to remove nodes and grids.

Manage Domain Folders Privilege

Users assigned the Manage Domain Folders privilege can create, edit, move, remove, and grant permission on domain folders.

The following table lists the required permissions and the actions that users can perform with the Manage Domain Folders privilege:

Permission On	Description
Domain or parent folder	User is able to create folders.
Folder	User is able to perform the following actions: <ul style="list-style-type: none">- Edit folders.- Grant permission on folders.
Original and destination folders	User is able to move folders from one parent folder to another.
Domain or parent folder and folder being removed	User is able to remove folders.

Manage Connections Privilege

Users assigned the Manage Connections privilege can create, edit, and delete connections in the Administrator tool, Analyst tool, Developer tool, and infacmd command line program. Users can also copy connections in the Developer tool and can grant permissions on connections in the Administrator tool and infacmd command line program.

Users assigned the Manage Connections privilege can create, edit, and delete connections in the Administrator tool, Developer tool, and infacmd command line program. Users can also copy connections in the Developer tool and can grant permissions on connections in the Administrator tool and infacmd command line program.

Users assigned connection permissions but not the Manage Connections privilege can perform the following connection management actions:

- View all connection metadata, except passwords. Requires read permission on connection.
- Preview data or run a mapping, scorecard, or profile. Requires execute permission on connection.
- Preview data or run a mapping or profile. Requires execute permission on connection.

The following table lists the required permissions and the actions that users can perform with the Manage Connections privilege:

Permission	Description
-	User is able to create connections.
Write on connection	User is able to copy, edit, and delete connections.
Grant on connection	User is able to grant and revoke permissions on connections.

Monitoring Privilege Group

The privileges in the Monitoring privilege group determine which users can view and configure monitoring.

The following table lists the required permissions and the actions that users can perform with the privileges in the Manage Monitoring group:

Parent Privilege	Privilege	Permission On	Description
Manage Monitoring	Monitoring Configuration	Domain	User can configure monitoring settings.
Manage Monitoring	Report and Statistic Settings	Domain	User can configure monitoring statistics and reports.
View	View Jobs of All the Users in the Groups the User Belongs To	Domain	A user in a group can monitor the jobs run by other users in the group. If the user belongs to multiple groups, the user can see the jobs from all the groups.
View Jobs of All the Users in the Groups the User Belongs To	View Jobs of Other Users	Domain	User can view jobs of other users.
View	View Statistics	Domain	User can view the Summary Statistics view and statistics for domain objects. Note: In a domain that uses Kerberos authentication, users must also have the Administrator role for the Model Repository Service that is configured for monitoring.
View	View Reports	Domain	User can view reports for domain objects.
Access Monitoring	Access from Analyst Tool	Domain	User can access the Job Status workspace in the Analyst tool.

Parent Privilege	Privilege	Permission On	Description
Access Monitoring	Access from Developer Tool	Domain	User can access the Monitoring tool from the Developer tool.
Access Monitoring	Access from Administrator Tool	Domain	User can access the Monitor tab in the Administrator tool.
N/A	Perform Actions on Jobs	Domain	User can perform the following actions: <ul style="list-style-type: none"> - Abort jobs. - Reissue mapping jobs. - View job logs.

Users do not need the Access Informatica Administrator privilege to access the Monitoring tool.

Tools Privilege Group

The privilege in the domain Tools group determines which users can access the Administrator tool.

The following table lists the required permissions and the actions that users can perform with the privilege in the Tools group:

Privilege	Description
Access Informatica Administrator	User is able to perform the following actions: <ul style="list-style-type: none"> - Log in to the Administrator tool. - Manage their own user account in the Administrator tool. - Export log events.

Users must have the Access Informatica Administrator privilege in order to complete tasks in the Administrator tool. Users do not need the Access Informatica Administrator privilege to run infacmd commands or access the Monitoring tool.

Cloud Administration Privilege Group

The privileges in the Cloud Administration group determine which users can view and configure Informatica Cloud organizations.

The following table lists the required permissions and the actions that users can perform with the privileges in the Cloud Administration group:

Privilege	Permission On	Description
View Organization	Domain	User can view the Informatica Cloud organizations and the associated Secure Agents and cloud connections.
Manage Organization	Domain	User can add Informatica Cloud organizations in the Administrator tool.

Analyst Service Privileges

The Analyst Service privilege determines actions that licensed users can perform on projects using the Analyst tool.

The following table lists the privileges and permissions required to manage projects and objects in projects:

Privilege	Permission	Description
Run Profiles and Scorecards	Read on projects. Execute on relational data source connection.	User is able to run profiles and scorecards for licensed users in the Analyst tool.
Access Mapping Specifications	Read on projects.	User is able to access mapping specifications for licensed users in the Analyst tool.
Load Mapping Specification Results	Write on projects.	User is able to load the results of a mapping specification for licensed users to a table or flat file. Note: Selecting this privilege also grants the Access Mapping Specifications privilege by default.
Manage Glossaries	-	User is able to manage the business glossary.
View Glossaries	-	User is able to view published Business Glossary assets in the Library workspace. This is equivalent to providing read permission for glossaries and Glossary assets in the Glossary Security workspace.
Workspace Access	-	User is able to access the following workspaces in the Analyst tool: <ul style="list-style-type: none">- Design workspace.- Discovery workspace.- Glossary workspace.- Scorecards workspace. Note: Selecting this privilege also grants access to projects in the Analyst tool. If the user does not have this privilege, the user must have either the Design Workspace , Discovery Workspace , Glossary Workspace , or Scorecards Workspace privilege to access projects.
Design Workspace	-	User is able to access the Design workspace.
Discovery Workspace	-	User is able to access the Discovery workspace.
Glossary Workspace	-	User is able to access the Glossary workspace.
Scorecards Workspace	-	User is able to access the Scorecards workspace.

Content Management Service Privileges

The Content Management Service privileges determine actions that licensed users can perform on reference tables.

The following table lists the privileges and permissions required to manage reference tables:

Privilege	Permission	Description
Create Reference Tables	Write on project	<ul style="list-style-type: none">- Create a reference table in the Analyst and Developer tool.- Create a reference table with infacmd rtm import.- Import a reference table object to the Model repository.- Copy a reference table in the Analyst and Developer tool.- Create a reference table from profile data. Note: The Create privilege also grants the Edit privilege by default.
Edit Reference Table Data and Metadata	Read on project	<ul style="list-style-type: none">- Edit reference table data values in the Developer tool and Analyst tool.- Add profile data to a reference table.- Add or delete columns in a reference table. Change reference table metadata such as column names, descriptions, and default values.

Data Integration Service Privileges

The Data Integration Service privileges determine actions that users can perform on applications using the Administrator tool and the infacmd command line program. They also determine whether users can drill down and export profile results using the Analyst tool and the Developer tool.

The Data Integration Service privileges determine actions that users can perform on applications using the Administrator tool and the infacmd command line program. They also determine whether users can drill down and export profile results using the Developer tool.

The following table lists the actions that users can perform with the privilege in the Application Administration privilege group:

Privilege Name	Description
Manage Applications	User is able to perform the following actions: <ul style="list-style-type: none">- Back up and restore an application to a file.- Deploy an application to a Data Integration Service and resolve name conflicts.- Start an application after deployment.- Find an application.- Start or stop objects in an application.- Configure application properties.

The following table lists the required permissions and the actions that users can perform with the privilege in the Profiling Administration privilege group:

Privilege Name	Permission On	Description
Drilldown and Export Results	Read on project Execute on relational data source connection is also required to drill down on live data	User is able to perform the following actions: - Drill down profiling results. - Export profiling results.

Metadata Manager Service Privileges

Metadata Manager Service privileges determine the Metadata Manager actions that users can perform using Metadata Manager.

The following table describes each Metadata Manager privilege group:

Privilege Group	Description
Catalog	Includes privileges to manage objects in the Browse page of the Metadata Manager interface.
Load	Includes privileges to manage objects in the Load page of the Metadata Manager interface.
Model	Includes privileges to manage objects in the Model page of the Metadata Manager interface.
Security	Includes privileges to manage objects in the Security page of the Metadata Manager interface.

Catalog Privilege Group

The privileges in the Catalog privilege group determine the tasks that users can perform on the **Browse** tab of the Metadata Manager application. A user with the privilege to perform a certain action also requires permissions to perform the action on a particular object. Configure permissions on the **Security** tab of the Metadata Manager application.

The following table lists the privileges in the Catalog privilege group and the permissions required to perform a task on an object:

Privilege	Includes Privileges	Permission	Description
Share Shortcuts	n/a	Write	User is able to share a folder that contains a shortcut with other users and groups.
View Lineage	n/a	Read	User is able to perform the following actions: - Run data lineage analysis on metadata objects, categories, and business terms. - Run data lineage analysis from the PowerCenter Designer. Users must also have read permission on the PowerCenter repository folder.

Privilege	Includes Privileges	Permission	Description
View Related Catalogs	n/a	Read	User is able to view related catalogs.
View Profile Results	n/a	Read	User is able to view profiling information for metadata objects in the catalog from a relational source.
View Catalog	n/a	Read	User is able to perform the following actions: <ul style="list-style-type: none"> - View resources and metadata objects in the metadata catalog. - Search the metadata catalog.
View Relationships	n/a	Read	User is able to view relationships for metadata objects, categories, and business terms.
Manage Relationships	View Relationships	Write	User is able to create, edit, and delete relationships for custom metadata objects, categories, and business terms.
View Comments	n/a	Read	User is able to view comments for metadata objects, categories, and business terms.
Post Comments	View Comments	Write	User is able to add comments for metadata objects, categories, and business terms.
Delete Comments	<ul style="list-style-type: none"> - Post Comments - View Comments 	Write	User is able to delete comments for metadata objects, categories, and business terms.
View Links	n/a	Read	User is able to view links for metadata objects, categories, and business terms.
Manage Links	View Links	Write	User is able to create, edit, and delete links for metadata objects, categories, and business terms.
View Glossary	n/a	Read	User is able to perform the following actions: <ul style="list-style-type: none"> - View business glossaries in the Glossary view. - Search business glossaries.
Manage Objects	n/a	Write	User is able to perform the following actions: <ul style="list-style-type: none"> - Edit metadata objects in the catalog. - Create, edit, and delete custom metadata objects. Users must also have the View Model privilege. - Create, edit, and delete custom metadata resources. Users must also have the Manage Resource privilege.

Load Privilege Group

The privileges in the Load privilege group determine the tasks that users can perform on the **Load** tab of the Metadata Manager application. A user with the privilege to perform a certain action also requires

permissions to perform the action on a particular object. Configure permissions on the **Security** tab of the Metadata Manager application.

The following table lists the privileges and permissions required to manage an instance of a resource in the Metadata Manager warehouse:

Privilege	Includes Privileges	Permission	Description
View Resource	-	Read	User is able to perform the following actions: <ul style="list-style-type: none"> - View resources and resource properties in the Metadata Manager warehouse. - Export resource configurations. - Download the Metadata Manager Agent installer.
Load Resource	View Resource	Write	User is able to perform the following actions: <ul style="list-style-type: none"> - Load metadata for a resource into the Metadata Manager warehouse.* - Create links between objects in connected resources for data lineage. - Configure search indexing for resources. - Import resource configurations.
Manage Schedules	View Resource	Write	User is able to perform the following actions: <ul style="list-style-type: none"> - Create and edit schedules. - Add schedules to resources.
Purge Metadata	View Resource	Write	User is able to remove metadata for a resource from the Metadata Manager warehouse.
Manage Resource	<ul style="list-style-type: none"> - Purge Metadata - View Resource 	Write	User is able to create, edit, and delete resources.
* To load metadata for Business Glossary resources, the Load Resource, Manage Resource, and View Model privileges are required.			

Model Privilege Group

The privileges in the Model privilege group determine the tasks that users can perform on the **Model** tab of the Metadata Manager application. You cannot configure permissions on a model.

The following table lists the privileges required to manage models:

Privilege	Includes Privileges	Permission	Description
View Model	-	-	User is able to open models and classes, and view model and class properties. View relationships and attributes for classes.
Manage Model	View Model	-	User is able to create, edit, and delete custom models. Add attributes to packaged and universal models.
Export/Import Models	View Model	-	User is able to import and export custom models. Import and export modified packaged and universal models.

Security Privilege Group

The privileges in the Security privilege group determines the tasks that users can perform on the **Security** tab of the Metadata Manager application.

By default, the Manage Catalog Permissions privilege in the Security privilege group is assigned to the Administrator, or a user with the Administrator role on the Metadata Manager Service. You can assign the Manage Catalog Permissions privilege to other users.

The following table lists the privilege and permission required to manage Metadata Manager security:

Privilege	Includes Privileges	Permission	Description
Manage Catalog Permissions	-	Full control	User is able to perform the following actions: <ul style="list-style-type: none">- Assign users and groups permissions on resources, metadata objects, categories, and business terms.- Edit permissions on resources, metadata objects, categories, and business terms.

Model Repository Service Privileges

The Model Repository Service privileges determine actions that users can perform on projects using Informatica Analyst and Informatica Developer.

The Model Repository Service privileges determine actions that users can perform on projects using Informatica Developer.

The Model repository object permissions determine the tasks that users can complete on objects in projects.

The following table lists the required permissions and the actions that users can perform with the Model Repository Service privileges:

Privilege	Permission	Description
N/A	Read on project	User can view projects and objects in projects.
N/A	Write on project	User can create, edit, and delete objects in projects.
N/A	Grant on project	User can grant and revoke permissions on projects for users and groups.
Access Analyst	N/A	User can access the Model repository from the Analyst tool.
Access Developer	N/A	User can access the Model repository from the Developer tool.
Create, Edit, and Delete Projects	N/A	User can create projects.

Privilege	Permission	Description
Create, Edit, and Delete Projects	Write on projects	User can perform the following actions: <ul style="list-style-type: none"> - Edit projects. - Delete projects if the user created the projects. - Upgrade the content of the Model Repository Service. To upgrade the service from the Actions menu or from the command line, the user must also have the Manage Service privilege for the domain and permission on the Model Repository Service. To upgrade the service using the service upgrade wizard, the user must also have the Administrator role for the domain.
Manage Data Domains	N/A	User can create, edit, and delete data domains in the data domain glossary. This privilege is part of the Data Domain Administration privilege group.
Manage Notifications	N/A	User can configure scorecard notifications. This privilege is part of the Profiling Administration privilege group.
Manage Team-based Development	N/A	User can manage the locked or unlocked states of Model repository objects. If the Model repository is integrated with a version control system, the user can manage the checked out or checked in states of objects. The user can also manage the ownership of checked-out objects.
Show Security Details	N/A	User can view the following details: <ul style="list-style-type: none"> - Names of projects for which users do not have read permission. - Error and warning message details.

Privilege	Permission	Description
N/A	Read on project	User can view projects and objects in projects.
N/A	Write on project	User can create, edit, and delete objects in projects.
N/A	Grant on project	User can grant and revoke permissions on projects for users and groups.
Access Developer	N/A	User can access the Model repository from the Developer tool.
Create, Edit, and Delete Projects	N/A	User can perform the following actions: <ul style="list-style-type: none"> - Create projects. - Upgrade the Model Repository Service.
Create, Edit, and Delete Projects	Write on project	User can perform the following actions: <ul style="list-style-type: none"> - Edit projects. - Delete projects if the user created the projects.
Show Security Details	N/A	User can view the following details: <ul style="list-style-type: none"> - Names of projects for which users do not have read permission. - Error and warning message details.

PowerCenter Repository Service Privileges

PowerCenter Repository Service privileges determine PowerCenter repository actions that users can perform using the PowerCenter Repository Manager, Designer, Workflow Manager, Workflow Monitor, and the `pmrep` and `pmcmd` command line programs.

The following table describes each privilege group for the PowerCenter Repository Service:

Privilege Group	Description
Tools	Includes privileges to access PowerCenter Client tools and command line programs.
Folders	Includes privileges to manage repository folders.
Design Objects	Includes privileges to manage business components, mapping parameters and variables, mappings, mapplets, transformations, and user-defined functions.
Sources and Targets	Includes privileges to manage cubes, dimensions, source definitions, and target definitions.
Run-time Objects	Includes privileges to manage session configuration objects, tasks, workflows, and worklets.
Global Objects	Includes privileges to manage connection objects, deployment groups, labels, and queries.

Users must have the Manage Services domain privilege and permission on the PowerCenter Repository Service to perform the following actions in the Repository Manager:

- Perform an advanced purge of object versions at the PowerCenter repository level.
- Create, edit, and delete reusable metadata extensions.

Tools Privilege Group

The privileges in the PowerCenter Repository Service Tools privilege group determine the PowerCenter Client tools and command line programs that users can access.

The following table lists the actions that users can perform for the privileges in the Tools group:

Privilege	Permission	Description
Access Designer	-	User is able to connect to the PowerCenter repository using the Designer.
Access Repository Manager	-	User is able to perform the following actions: <ul style="list-style-type: none">- Connect to the PowerCenter repository using the Repository Manager.- Run <i>pmrep</i> commands.
Access Workflow Manager	-	User is able to perform the following actions: <ul style="list-style-type: none">- Connect to the PowerCenter repository using the Workflow Manager.- Remove a PowerCenter Integration Service from the Workflow Manager.
Access Workflow Monitor	-	User is able to perform the following actions: <ul style="list-style-type: none">- Connect to the PowerCenter repository using the Workflow Monitor.- Connect to the PowerCenter Integration Service in the Workflow Monitor.

Note: When the PowerCenter Integration Service runs in safe mode, users must have the Administrator role for the associated PowerCenter Repository Service.

The appropriate privilege in the Tools privilege group is required for all users completing tasks in PowerCenter Client tools and command line programs. For example, to create folders in the Repository Manager, a user must have the Create Folders and Access Repository Manager privileges.

If users have a privilege in the Tools privilege group and permission on a PowerCenter repository object but not the privilege to modify the object type, they can still perform some actions on the object. For example, a user has the Access Repository Manager privilege and read permission on some folders. The user does not have any of the privileges in the Folders privilege group. The user can view objects in the folders and compare the folders.

Folders Privilege Group

Folder management actions are determined by privileges in the Folders privilege group, PowerCenter repository object permissions, and domain object permissions. Users perform folder management actions in the Repository Manager and with the pmrep command line program.

Some folder management tasks are determined by folder ownership and the Administrator role, not by privileges or permissions. The folder owner or a user assigned the Administrator role for the PowerCenter Repository Service can complete the following folder management tasks:

- Assign operating system profiles to folders if the PowerCenter Integration Service uses operating system profiles. Requires permission on the operating system profile.
- Change the folder owner.
- Configure folder permissions.
- Delete the folder.
- Designate the folder to be shared.
- Edit the folder name and description.

Users assigned folder permissions but no privileges can perform some folder management actions. The following table lists the actions that users can perform when they are assigned folder permissions only:

Permission	Description
Read on folder	User is able to perform the following actions: <ul style="list-style-type: none">- Compare folders.- View objects in folders.

Note: To perform actions on folders, users must also have the Access Repository Manager privilege.

Create Folders Privilege

Users assigned the Create Folders privilege can create PowerCenter repository folders.

The following table lists the required permissions and the actions that users can perform with the Create Folders privilege:

Permission	Description
-	User is able to create folders.

Copy Folders Privilege

Users assigned the Copy Folders privilege can copy folders within a PowerCenter repository or to another PowerCenter repository.

The following table lists the required permissions and the actions that users can perform with the Copy Folders privilege:

Permission	Description
Read on folder	User is able to copy folders within the same PowerCenter repository or to another PowerCenter repository. Users must also have the Create Folders privilege in the destination repository.

Manage Folder Versions

If you have a team-based development option, assign users the Manage Folder Versions privilege in a versioned PowerCenter repository. Users can change the status of folders and perform an advanced purge of object versions at the folder level.

The following table lists the required permissions and the actions that users can perform with the Manage Folder Versions privilege:

Permission	Description
Read and Write on folder	User is able to perform the following actions: <ul style="list-style-type: none">- Change the status of folders.- Perform an advanced purge of object versions at the folder level.

Design Objects Privilege Group

Privileges in the Design Objects privilege group and PowerCenter repository object permissions determine actions users can perform on the following design objects:

- Business components
- Mapping parameters and variables
- Mappings
- Mapplets
- Transformations
- User-defined functions

Users assigned permissions but no privileges can perform some actions for design objects. The following table lists the actions that users can perform when they are assigned permissions only:

Permission	Description
Read on folder	User is able to perform the following actions: <ul style="list-style-type: none">- Compare design objects.- Copy design objects as an image.- Export design objects.- Generate code for Custom transformation and external procedures.- Receive PowerCenter repository notification messages.- Run data lineage on design objects. Users must also have the View Lineage privilege for the Metadata Manager Service and read permission on the metadata objects in the Metadata Manager catalog.- Search for design objects.- View design objects, design object dependencies, and design object history.
Read on shared folder Read and Write on destination folder	User is able to create shortcuts.

Note: To perform actions on design objects, users must also have the appropriate privilege in the Tools privilege group.

Create, Edit, and Delete Design Objects Privilege

Users assigned the Create, Edit, and Delete Design Objects privilege can create, edit, and delete business components, mapping parameters, mapping variables, mappings, mapplets, transformations, and user-defined functions.

The following table lists the required permissions and the actions that users can perform with the Create, Edit, and Delete Design Objects privilege:

Permission	Description
Read on original folder Read and Write on destination folder	User is able to perform the following actions: <ul style="list-style-type: none">- Copy design objects from one folder to another.- Copy design objects to another PowerCenter repository. Users must also have the Create, Edit, and Delete Design Objects privilege in the destination repository.
Read and Write on folder	User is able to perform the following actions: <ul style="list-style-type: none">- Change comments for a versioned design object.- Check in and undo a checkout of design objects checked out by their own user account.- Check out design objects.- Copy and paste design objects in the same folder.- Create, edit, and delete data profiles and launch the Profile Manager. Users must also have the Create, Edit, and Delete Run-time Objects privilege.- Create, edit, and delete design objects.- Generate and clean SAP ABAP programs.- Generate business content integration mappings. Users must also have the Create, Edit, and Delete Sources and Targets privilege.- Import design objects using the Designer. Users must also have the Create, Edit, and Delete Sources and Targets privilege.- Import design objects using the Repository Manager. Users must also have the Create, Edit, and Delete Run-time Objects and Create, Edit, and Delete Sources and Targets privileges.- Revert to a previous design object version.- Validate mappings, mapplets, and user-defined functions.

Manage Design Object Versions

If you have a team-based development option, assign users the Manage Design Object Versions privilege in a versioned PowerCenter repository. Users can change the status, recover, and purge design object versions. Users can also check in and undo checkouts made by other users.

The Manage Design Object Versions privilege includes the Create, Edit, and Delete Design Objects privilege.

The following table lists the required permissions and the actions that users can perform with the Manage Design Object Versions privilege:

Permission	Description
Read and Write on folder	<p>User is able to perform the following actions:</p> <ul style="list-style-type: none"> - Change the status of design objects. - Check in and undo checkouts of design objects checked out by other users. - Purge versions of design objects. - Recover deleted design objects.

Sources and Targets Privilege Group

Privileges in the Sources and Targets privilege group and PowerCenter repository object permissions determine actions users can perform on the following source and target objects:

- Cubes
- Dimensions
- Source definitions
- Target definitions

Users assigned permissions but no privileges can perform some actions for source and target objects. The following table lists the actions that users can perform when they are assigned permissions only:

Permission	Description
Read on folder	<p>User is able to perform the following actions:</p> <ul style="list-style-type: none"> - Compare source and target objects. - Export source and target objects. - Preview source and target data. - Receive PowerCenter repository notification messages. - Run data lineage on source and target objects. Users must also have the View Lineage privilege for the Metadata Manager Service and read permission on the metadata objects in the Metadata Manager catalog. - Search for source and target objects. - View source and target objects, source and target object dependencies, and source and target object history.
Read on shared folder Read and Write on destination folder	Create shortcuts.

Note: To perform actions on source and target objects, users must also have the appropriate privilege in the Tools privilege group.

Create, Edit, and Delete Sources and Targets Privilege

Users assigned the Create, Edit, and Delete Sources and Targets privilege can create, edit, and delete cubes, dimensions, source definitions, and target definitions.

The following table lists the required permissions and the actions that users can perform with the Create, Edit, and Delete Sources and Targets privilege:

Permission	Description
Read on original folder Read and Write on destination folder	User is able to perform the following actions: <ul style="list-style-type: none">- Copy source and target objects to another folder.- Copy source and target objects to another PowerCenter repository. Users must also have the Create, Edit, and Delete Sources and Targets privilege in the destination repository.
Read and Write on folder	User is able to perform the following actions: <ul style="list-style-type: none">- Change comments for a versioned source or target object.- Check in and undo a checkout of source and target objects checked out by their own user account.- Check out source and target objects.- Copy and paste source and target objects in the same folder.- Create, edit, and delete source and target objects.- Import SAP functions.- Import source and target objects using the Designer. Users must also have the Create, Edit, and Delete Design Objects privilege.- Import source and target objects using the Repository Manager. Users must also have the Create, Edit, and Delete Design Objects and Create, Edit, and Delete Run-time Objects privileges.- Generate and execute SQL to create targets in a relational database.- Revert to a previous source or target object version.

Manage Source and Target Versions Privilege

If you have a team-based development option, assign users the Manage Source and Target Versions privilege in a versioned PowerCenter repository. Users can change the status, recover, and purge versions of source and target objects. Users can also check in and undo checkouts made by other users.

The Manage Source and Target Versions privilege includes the Create, Edit, and Delete Sources and Targets privilege.

The following table lists the required permissions and the actions that users can perform with the Manage Source and Target Versions privilege:

Permission	Description
Read and Write on folder	User is able to perform the following actions: <ul style="list-style-type: none">- Change the status of source and target objects.- Check in and undo checkouts of source and target objects checked out by other users.- Purge versions of source and target objects.- Recover deleted source and target objects.

Run-time Objects Privilege Group

Privileges in the Run-time Objects privilege group, PowerCenter repository object permissions, and domain object permissions determine actions users can perform on the following run-time objects:

- Session configuration objects
- Tasks
- Workflows
- Worklets

Some run-time object tasks are determined by the Administrator role, not by privileges or permissions. A user assigned the Administrator role for the PowerCenter Repository Service can delete a PowerCenter Integration Service from the Navigator of the Workflow Manager.

Users assigned permissions but no privileges can perform some actions for run-time objects. The following table lists the actions that users can perform when they are assigned permissions only:

Permission	Description
Read on folder	User is able to perform the following actions: <ul style="list-style-type: none">- Compare run-time objects.- Export run-time objects.- Receive PowerCenter repository notification messages.- Search for run-time objects.- Use mapping parameters and variables in a session.- View run-time objects, run-time object dependencies, and run-time object history.
Read and Execute on folder	Stop and abort tasks and workflows started by their own user account. When the PowerCenter Integration Service runs in safe mode, users must have the Administrator role for the associated PowerCenter Repository Service.

Note: To perform actions on run-time objects, users must also have the appropriate privilege in the Tools privilege group.

Create, Edit, and Delete Run-time Objects Privilege

Users assigned the Create, Edit, and Delete Run-time Objects privilege can create, edit, and delete session configuration objects, tasks, workflows, and worklets.

The following table lists the required permissions and the actions that users can perform with the Create, Edit, and Delete Run-time Objects privilege:

Permission	Description
Read on original folder Read and Write on destination folder	User is able to perform the following actions: <ul style="list-style-type: none">- Copy tasks, workflows, or worklets from one folder to another.- Copy tasks, workflows, or worklets to another PowerCenter repository. Users must also have the Create, Edit, and Delete Run-time Objects privilege in the destination repository.
Read and Write on folder	User is able to perform the following actions: <ul style="list-style-type: none">- Assign a PowerCenter Integration Service to a workflow in the workflow properties.- Assign a service level to a workflow.- Change comments for a versioned run-time object.- Check in and undo a checkout of run-time objects checked out by their own user account.- Check out run-time objects.- Copy and paste tasks, workflows, and worklets in the same folder.- Create, edit, and delete data profiles and launch the Profile Manager. Users must also have the Create, Edit, and Delete Design Objects privilege.- Create, edit, and delete session configuration objects.- Delete and validate tasks, workflows, and worklets.- Import run-time objects using the Repository Manager. Users must also have the Create, Edit, and Delete Design Objects and Create, Edit, and Delete Sources and Targets privileges.- Import run-time objects using the Workflow Manager.- Revert to a previous object version.
Read and Write on folder Read on connection object	User is able to perform the following actions: <ul style="list-style-type: none">- Create and edit tasks, workflows, and worklets.- Replace a relational database connection for all sessions that use the connection.

Manage Run-time Object Versions Privilege

If you have a team-based development option, assign users the Manage Run-time Object Versions privilege in a versioned PowerCenter repository. Users can change the status, recover, and purge run-time object versions. Users can also check in and undo checkouts made by other users.

The Manage Run-time Object Versions privilege includes the Create, Edit, and Delete Run-time Objects privilege.

The following table lists the required permissions and the actions that users can perform with the Manage Run-time Object Versions privilege:

Permission	Description
Read and Write on folder	<p>User is able to perform the following actions:</p> <ul style="list-style-type: none"> - Change the status of run-time objects. - Check in and undo checkouts of run-time objects checked out by other users. - Purge versions of run-time objects. - Recover deleted run-time objects.

Monitor Run-time Objects Privilege

Users assigned the Monitor Run-time Objects privilege can Monitor workflows and tasks in the Workflow Monitor.

The following table lists the required permissions and the actions that users can perform with the Monitor Run-time Objects privilege:

Permission	Grants Users the Ability To
Read on folder	<p>User is able to perform the following actions:</p> <ul style="list-style-type: none"> - View properties of run-time objects in the Workflow Monitor. - View session and workflow logs in the Workflow Monitor. - View run-time object and performance details in the Workflow Monitor. <p>When the PowerCenter Integration Service runs in safe mode, users must have the Administrator role for the associated PowerCenter Repository Service.</p>

Execute Run-time Objects Privilege

Users assigned the Execute Run-time Objects privilege can start, cold start, and recover tasks and workflows.

The Execute Run-time Objects privilege includes the Monitor Run-time Objects privilege.

The following table lists the required permissions and the actions that users can perform with the Execute Run-time Objects privilege:

Permission	Description
Read and Execute on folder	User is able to assign a PowerCenter Integration Service to a workflow using the Service menu or the Navigator.
Read, Write, and Execute on folder Read and Execute on connection object	<p>User is able to debug a mapping by creating a debug session instance or by using an existing reusable session. Users must also have the Create, Edit, and Delete Run-time Objects privilege.</p> <p>When the PowerCenter Integration Service runs in safe mode, users must have the Administrator role for the associated PowerCenter Repository Service.</p>

Permission	Description
Read and Execute on folder Read and Execute on connection object	User is able to debug a mapping by using an existing non-reusable session. When the PowerCenter Integration Service runs in safe mode, users must have the Administrator role for the associated PowerCenter Repository Service.
Read and Execute on folder Read and Execute on connection object	User is able to perform the following actions: <ul style="list-style-type: none"> - Start, cold start, and restart tasks and workflows. - Recover tasks and workflows started by their own user account. If the PowerCenter Integration Service uses operating system profiles, users must also have permission on the operating system profile. When the PowerCenter Integration Service runs in safe mode, users must have the Administrator role for the associated PowerCenter Repository Service.

Manage Run-time Object Execution Privilege

Users assigned the Manage Run-time Object Execution privilege can schedule and unschedule workflows. Users can also stop, abort, and recover tasks and workflows started by other users.

The Manage Run-time Object Execution privilege includes the Execute Run-time Objects privilege and the Monitor Run-time Objects privilege.

The following table lists the required permissions and the actions that users can perform with the Manage Run-time Object Execution privilege:

Permission	Description
Read and Execute on folder	User is able to truncate workflow and session log entries.
Read and Execute on folder	User is able to perform the following actions: <ul style="list-style-type: none"> - Stop and abort tasks and workflows started by other users. - Stop and abort tasks that were recovered automatically. - Unschedule workflows. When the PowerCenter Integration Service runs in safe mode, users must have the Administrator role for the associated PowerCenter Repository Service.
Read and Execute on folder Read and Execute on connection object	User is able to perform the following actions: <ul style="list-style-type: none"> - Recover tasks and workflows started by other users. - Recover tasks that were recovered automatically. If the PowerCenter Integration Service uses operating system profiles, users must also have permission on the operating system profile. When the PowerCenter Integration Service runs in safe mode, users must have the Administrator role for the associated PowerCenter Repository Service.
Read, Write, and Execute on folder Read and Execute on connection object	User is able to perform the following actions: <ul style="list-style-type: none"> - Create and edit a reusable scheduler from the Workflows > Schedulers menu. - Edit a non-reusable scheduler from the workflow properties. - Edit a reusable scheduler from the workflow properties. Users must also have the Create, Edit, and Delete Run-time Objects privilege. If the PowerCenter Integration Service uses operating system profiles, users must also have permission on the operating system profile. When the PowerCenter Integration Service runs in safe mode, users must have the Administrator role for the associated PowerCenter Repository Service.

Global Objects Privilege Group

Privileges in the Global Objects privilege group and PowerCenter repository object permissions determine actions users can perform on the following global objects:

- Connection objects
- Deployment groups
- Labels
- Queries

Some global object tasks are determined by global object ownership and the Administrator role, not by privileges or permissions. The global object owner or a user assigned the Administrator role for the PowerCenter Repository Service can complete the following global object tasks:

- Configure global object permissions.
- Change the global object owner.
- Delete the global object.

Users assigned permissions but no privileges can perform some actions for global objects. The following table lists the actions that users can perform when they are assigned permissions only:

Permission	Description
Read on connection object	User is able to view connection objects.
Read on deployment group	User is able to view deployment groups.
Read on label	User is able to view labels.
Read on query	User is able to view object queries.
Read and Write on connection object	User is able to edit connection objects.
Read and Write on label	User is able to edit and lock labels.
Read and Write on query	User is able to edit and validate object queries.
Read and Execute on query	User is able to run object queries.
Read on folder Read and Execute on label	User is able to apply labels and remove label references.

Note: To perform actions on global objects, users must also have the appropriate privilege in the Tools privilege group.

Create Connections Privilege

Users assigned the Create Connections privilege can create connection objects.

The following table lists the required permissions and the actions that users can perform with the Create Connections privilege:

Permission	Description
-	User is able to create and copy connection objects.

Manage Deployment Groups Privilege

If you have a team-based development option, users assigned the Manage Deployment Groups privilege in a versioned PowerCenter repository can create, edit, copy, and roll back deployment groups. In a non-versioned repository, users can create, edit, and copy deployment groups.

The following table lists the required permissions and the actions that users can perform with the Manage Deployment Groups privilege:

Permission	Description
-	User is able to create deployment groups.
Read and Write on deployment group	User is able to perform the following actions: <ul style="list-style-type: none">- Edit deployment groups.- Remove objects from a deployment group.
Read on original folder Read and Write on deployment group	User is able to add objects to a deployment group.
Read on original folder Read and Write on destination folder Read and Execute on deployment group	User is able to copy deployment groups.
Read and Write on destination folder	User is able to roll back deployment groups.

Execute Deployment Groups Privilege

Users assigned the Execute Deployment Groups privilege can copy a deployment group without write permission on target folders.

The following table lists the required permissions and the actions that users can perform with the Execute Deployment Groups privilege:

Permission	Description
Read on original folder Execute on deployment group	User is able to copy deployment groups.

Create Labels Privilege

If you have a team-based development option, users assigned the Create Labels privilege in a versioned PowerCenter repository can create labels.

The following table lists the required permissions and the actions that users can perform with the Create Labels privilege:

Permission	Description
-	User is able to create labels.

Create Queries Privilege

Users assigned the Create Queries privilege can create object queries.

The following table lists the required permissions and the actions that users can perform with the Create Queries privilege:

Permission	Description
-	User is able to create object queries.

PowerExchange Listener Service Privileges

The PowerExchange Listener Service privileges determine the infacmd pwx commands that users can run.

The following table describes the PowerExchange Listener Service privilege in the Informational Commands privilege group:

Privilege Name	Description
listtask	Run the infacmd pwx ListTaskListener command.

The following table describes each PowerExchange Listener Service privilege in the Management Commands privilege group:

Privilege Name	Description
close	Run the infacmd pwx CloseListener command.
closeforce	Run the infacmd pwx CloseForceListener command.
stoptask	Run the infacmd pwx StopTaskListener command.

PowerExchange Logger Service Privileges

The PowerExchange Logger Service privileges determine the infacmd pwx commands that users can run.

The following table describes each PowerExchange Logger Service privilege in the Informational Commands privilege group:

Privilege Name	Description
displayall	Run the infacmd pwx DisplayAllLogger command.
displaycpu	Run the infacmd pwx DisplayCPULogger command.
displaycheckpoints	Run the infacmd pwx DisplayCheckpointsLogger command.
displayevents	Run the infacmd pwx DisplayEventsLogger command.
displaymemory	Run the infacmd pwx DisplayMemoryLogger command.
displayrecords	Run the infacmd pwx DisplayRecordsLogger command.
displaystatus	Run the infacmd pwx DisplayStatusLogger command.

The following table describes each PowerExchange Logger Service privilege in the Management Commands privilege group:

Privilege Name	Description
condense	Run the infacmd pwx CondenseLogger command.
fileswitch	Run the infacmd pwx FileSwitchLogger command.
shutdown	Run the infacmd pwx ShutDownLogger command.

Scheduler Service Privileges

Scheduler Service privileges determine the actions that users can perform on schedules and scheduled jobs.

The following table describes the Scheduler Service privileges and required permissions:

Privilege	Description	Requires Permission On
Create Schedule	User can create schedules. To create a schedule, the user must also have the Application Administration privilege on the Data Integration Service.	<ul style="list-style-type: none">- Scheduler Service- Data Integration Service that runs the jobs that the user wants to schedule
Edit Schedule	User can edit, pause, and resume schedules. To edit a schedule, the user must also have the Application Administration privilege on the Data Integration Service.	<ul style="list-style-type: none">- Scheduler Service- Data Integration Service that runs the jobs that the user wants to schedule
Delete Schedule	User can delete schedules.	Scheduler Service
View Schedules	User can view the Schedules view and schedules.	Scheduler Service

Test Data Manager Service Privileges

Test Data Manager Service privileges determine the actions that users can perform using Test Data Manager. Configure privileges on the **Security** tab of the Administrator tool.

The following table describes each Test Data Manager privilege group:

Privilege Group	Description
Administration	Includes privileges to create and manage connections, roles and assign privileges to users and user groups from the Informatica Administrator, manage repositories, add licenses, and set up workflow and project attributes. Note: Before you can create users and groups, the default Informatica administrator user must assign Security Administration privileges to the Test Data Administrator user.
Data Domains	Includes privileges to view and manage data domains in the Test Data Manager.
Data Masking	Includes privileges to view and manage masking rules and policy assignments in the Test Data Manager.
Data Subset	Includes privileges to view and manage subset objects including entities, groups and templates in the Test Data Manager.
Policies	Includes privileges to view and manage policies in the Test Data Manager.
Projects	Includes privileges to view and manage projects, audit and import metadata, and execute plans and workflows in the Test Data Manager.

Privilege Group	Description
Rules	Includes privileges to view and manage masking and generation rules in the Test Data Manager.
Data Generation	Includes privileges to view and manage test data generation in the Test Data Manager.

Administration Privilege Group

The privileges in the Administration privilege group determine the administration tasks that Test Data Administrators can perform.

The following table lists the privileges in the Administration privilege group and the permissions required to perform a task on an object:

Privilege	Includes Privileges	Permission	Description
Manage Preferences	-	Write	<p>User can perform the following actions on the Informatica Administrator and Test Data Manager:</p> <ul style="list-style-type: none"> - Create roles. - Edit roles. - Delete roles. - View roles. - Associate roles to users. - Associate privileges to users. - Associate roles to user groups. - Associate privileges to user groups. - Add licenses. - Set up the TDM repository. - Set up the PowerCenter repository. - Set up data domain sensitivity levels. - Configure a test data warehouse repository. - Configure a test data warehouse. - Set up project custom attributes. - Set up workflow generation attributes. - Enable data discovery. - Set up profiling services. - View administration objects. - Configure keyword search indexing options.
View Connections	-	Read	<p>User can perform the following actions on the Connections page in the Test Data Manager:</p> <ul style="list-style-type: none"> - View connections. - Test connections.
Manage Connections	View Connections	Write	<p>User can perform the following actions on the Connections page in the Test Data Manager:</p> <ul style="list-style-type: none"> - Create connections. - Edit connections. - Delete connections. - View connections. - Test connections. - Configure a test data warehouse repository. - Configure a test data warehouse.

Connections Privilege Group

The privileges in the Connections privilege group determine the tasks that users can perform on the Connections page of the TDM Workbench. The following table lists the privileges in the Connections privilege group and the permissions required to perform a task on an object:

Privilege	Includes Privileges	Permission	Description
View Connections	-	Read	User can view connections and test connections in the TDM Workbench.
Manage Connections	View Connections	Write	User can perform the following actions on the Connections page in the TDM Workbench: <ul style="list-style-type: none">- Create connections.- Edit connections.- Delete connections.- View connections.- Test connections.

Data Domains Privilege Group

The privileges in the Data Domains privilege group determine the tasks that users can perform on data domains on the Policies page of the Test Data Manager.

The following table lists the privileges in the Data Domains privilege group and the permissions required to perform a task on an object:

Privilege	Includes Privileges	Permission	Description
View Data Domains	-	Read	User can view data domains in the Test Data Manager.
Manage Data Domains	View Data Domains	Write	User can perform the following actions on data domains in the Test Data Manager: <ul style="list-style-type: none">- Create data domains.- Edit data domains.- Delete data domains.- View data domains.

Data Masking Privilege Group

The privileges in the Data Masking privilege group determine the tasks that users can perform on the Project | Define | Data Masking view of the Test Data Manager. You can assign rules and policies to table columns from this view.

The following table lists the privileges in the Data Masking privilege group and the permissions required to perform a task on an object:

Privilege	Includes Privileges	Permission	Description
View Data Masking	-	Read	User can view data masking assignments in the Test Data Manager.
Manage Data Masking	View Data Masking	Write	User can perform the following data masking assignment actions in the Test Data Manager: <ul style="list-style-type: none">- Add rule and policy assignments.- Delete rule and policy assignments.- Override rule properties.- View data masking assignments.

Data Subset Privilege Group

The privileges in the Data Subset privilege group determine the tasks that users can perform on data subset objects in the Test Data Manager.

The following table lists the privileges in the Data Subset privilege group and the permissions required to perform a task on an object:

Privilege	Includes Privileges	Permission	Description
View Data Subset	-	Read	User can perform the following data subset actions in the Test Data Manager: <ul style="list-style-type: none">- View groups.- View templates- View entities.- View recent project objects.
Manage Data Subset	View Data Subset	Write	User can perform the following data subset actions in the Test Data Manager: <ul style="list-style-type: none">- Create groups.- Edit groups.- Delete groups.- Add group parameters.- Create templates.- Edit templates.- Delete templates.- Add template parameters.- Create entity.- Edit entity.- Delete entity.- Add entity criteria.- Enable relationships.- Disable relationships.- Edit relationships- Review and act on changes.- Mark change review as complete.

Policies Privilege Group

The privileges in the Policies privilege group determine the tasks that users can perform on Policies in the Test Data Manager.

The following table lists the privileges in the Policies privilege group and the permissions required to perform a task on an object:

Privilege	Includes Privileges	Permission	Description
View Policies	-	Read	User can view policies in the Test Data Manager.
Manage Policies	View Policies	Write	User can perform the following policy actions policies in the Test Data Manager: <ul style="list-style-type: none">- Create policies.- Edit policies.- Delete policies.- View policies.

Projects Privilege Group

The privileges in the Projects privilege group determine the tasks that users can perform on Projects in the Test Data Manager.

The following table lists the privileges in the Projects privilege group and the permissions required to perform a task on an object:

Privilege	Includes Privileges	Permission	Description
View Project	-	Read	User can perform the following actions on projects in the Test Data Manager: <ul style="list-style-type: none">- View projects.- View plans.- View plan detail reports.- View plan audit reports.- View recent projects.- Create test data warehouse plans- Manage test data warehouse plans- Generate test data warehouse plans- Execute test data warehouse plans
Manage Project	View Project	Write	User can perform the following actions on projects in the Test Data Manager: <ul style="list-style-type: none">- Create projects- Edit projects.- Delete projects- View projects.- Associate users to projects.- Associate user groups to projects.- Associate or remove rules to projects.- Associate or remove policies to projects- Create plans.- Edit plans.- Delete plans.- Generate plans.

Privilege	Includes Privileges	Permission	Description
Discover Project	-	Write	<p>User can perform the following discover actions on projects in the Test Data Manager:</p> <ul style="list-style-type: none"> - Classify tables. - Mark discovery as complete. - Associate data domains to columns. - Mark columns as restricted. - Mark columns as sensitive - Set similar value column - Remove similar value columns - Add primary keys - Remove primary Keys - Create logical constraints - View logical constraints - Edit logical Constraints - Delete Logical Constraints - View projects. - View profiled data domains. - Approve or reject profile data domains. - Mark data domain classification as complete. - View profiled primary keys. - Approve or reject profiled primary keys. - Mark primary key discovery as complete. - View profiled entities. - Approve or reject profiled entities. - Mark entity discovery as complete. - View project risk analysis. - View recent project sensitive data distribution.
Generate Project	-	Write	User can generate workflows in the Test Data Manager.
Execute Project	-	Write	<p>User can perform the following execute actions on projects in the Test Data Manager:</p> <ul style="list-style-type: none"> - Execute plans. - Execute workflows. - Stop workflows. - Abort workflows. - Recover workflows. - View plan execution.
Monitor Project	-	Read	<p>User can perform the following monitor actions on projects in the Test Data Manager:</p> <ul style="list-style-type: none"> - Monitor project jobs. - View project job logs. - Monitor jobs across projects. - View job logs across projects.
Audit Project	-	Read	User can view recent activity on projects and plans in the Test Data Manager.
Import Metadata	-	Write	<p>User can perform the following actions on projects in the Test Data Manager:</p> <ul style="list-style-type: none"> - Import sources - Delete sources.

Note: A user with Manage Project privilege must have at least the following levels of privileges to be able to create a plan with each component.

- View connection from the Administration privilege group. To create a plan.
- View data subset from the Data Subset privilege group. To create a plan with subset components.
- View masking rules from the Rules privilege group. To create a plan with masking components.
- View generation rules from the Rules privilege group. To create a plan with generation components.

Rules Privilege Group

The privileges in the Rules privilege group determine the tasks that users can perform on data masking and data generation rules in the Test Data Manager.

The following table lists the privileges in the Data Masking privilege group and the permissions required to perform a task on an object:

Privilege	Includes Privileges	Permission	Description
View Masking Rules	-	Read	User can view masking rules in the Test Data Manager.
Manage Masking Rules	View Masking Rules	Write	User can perform the following actions on data masking rules in the Test Data Manager: <ul style="list-style-type: none">- Create masking rules.- Edit masking rules.- Delete masking rules.- View masking rules.
View Generation Rules	-	Read	User can view generation rules in the Test Data Manager.
Manage Generation Rules	View Generation Rules	Write	User can perform the following actions on data generation rules in the Test Data Manager: <ul style="list-style-type: none">- Create generation rules.- Edit generation rules.- Delete generation rules.- View generation rules.

Data Generation Privilege Group

The privileges in the Data Generation privilege group determine the test data generation tasks that users can perform in the Test Data Manager.

The following table lists the privileges in the Data Generation privilege group and the permissions required to perform a task on an object:

Privilege	Includes Privileges	Permission	Description
View Data Generation	-	Read	User can view data generation rule assignments in the Test Data Manager.
Manage Data Generation	View Data Generation	Write	User can perform the following actions on data generation in the Test Data Manager: <ul style="list-style-type: none">- View data generation rule assignments- Add data generation rule assignments.- Delete data generation rule assignments.- Override data generation rule assignments.

Managing Roles

A role is a collection of privileges that you can assign to users and groups. You can assign the following types of roles:

- System-defined. Roles that you cannot edit or delete.
- Custom. Roles that you can create, edit, and delete.

A role includes privileges for the domain or an application service type. You assign roles to users or groups for the domain or for each application service in the domain. For example, you can create a Developer role that includes privileges for the PowerCenter Repository Service. A domain can contain multiple PowerCenter Repository Services. You can assign the Developer role to a user for the Development PowerCenter Repository Service. You can assign a different role to that user for the Production PowerCenter Repository Service.

A role includes privileges for the domain or an application service type. You assign roles to users or groups for the domain or for each application service in the domain.

A role includes privileges for the domain or an application service type. You assign roles to users or groups for the domain or for each application service in the domain.

UMSM has the following types of roles:

- Administrator. This is a system-defined role that has privileges to administer the Administrator tool. With this role, you can create and manage user accounts, create the Ultra Messaging Service and configure it, configure UMSM components, and UM deployments.
- Operator. This is a custom role that has privileges to monitor UM deployments.

When you select a role in the Roles section of the Navigator, you can view all users and groups that have been directly assigned the role for the domain and application services. You can view the role assignments by users and groups or by services. To navigate to a user or group listed in the Assignments section, right-click the user or group and select **Navigate to Item**.

You can search for system-defined and custom roles.

System-Defined Roles

A system-defined role is a role that you cannot edit or delete. The Administrator role is a system-defined role.

When you assign the Administrator role to a user or group for the domain, Analyst Service, Data Integration Service, Metadata Manager Service, Model Repository Service, or PowerCenter Repository Service, the user or group is granted all privileges for the service. The Administrator role bypasses permission checking. Users with the Administrator role can access all objects managed by the service.

When you assign the Administrator role to a user or group for the domain, Data Integration Service, Model Repository Service, the user or group is granted all privileges for the service. The Administrator role bypasses permission checking. Users with the Administrator role can access all objects managed by the service.

When you assign the Administrator role to a user or group for the domain or Ultra Messaging Service, the user or group is granted all privileges for the service. The Administrator role bypasses permission checking. Users with the Administrator role can access all objects managed by the service.

Administrator Role

When you assign the Administrator role to a user or group for the domain, Data Integration Service, or PowerCenter Repository Service, the user or group can complete some tasks that are determined by the Administrator role, not by privileges or permissions.

When you assign the Administrator role to a user or group for the domain or Data Integration Service, the user or group can complete some tasks that are determined by the Administrator role, not by privileges or permissions.

When you assign the Administrator role to a user or group for the domain or Ultra Messaging Service, the user or group can complete some tasks that are determined by the Administrator role, not by privileges or permissions.

You can assign a user or group all privileges for the domain, Data Integration Service, or PowerCenter Repository Service and then grant the user or group full permissions on all domain or PowerCenter repository objects. However, this user or group cannot complete the tasks determined by the Administrator role.

You can assign a user or group all privileges for the domain or Data Integration Service and then grant the user or group full permissions on all domain objects. However, this user or group cannot complete the tasks determined by the Administrator role.

You can assign a user or group all privileges for the domain or Ultra Messaging Service and then grant the user or group full permissions on all domain objects. However, this user or group cannot complete the tasks determined by the Administrator role.

For example, a user assigned the Administrator role for the domain can configure domain properties in the Administrator tool. A user assigned all domain privileges and permission on the domain cannot configure domain properties.

The following table lists the tasks determined by the Administrator role for the domain, Data Integration Service, and PowerCenter Repository Service:

The following table lists the tasks determined by the Administrator role for the domain or Data Integration Service:

The following table lists the tasks determined by the Administrator role for the domain or Ultra Messaging Service:

Service	Tasks
Domain	<ul style="list-style-type: none"> - Configure domain properties. - Create operating system profiles. - Delete operating system profiles. - Grant permission on the domain and operating system profiles. - Manage and purge log events. - Receive domain alerts. - Run the License Report. - View user activity log events. - Shut down the domain. - Access the service upgrade wizard.
Data Integration Service	<ul style="list-style-type: none"> - Upgrade the Data Integration Service using the Actions menu.
PowerCenter Repository Service	<ul style="list-style-type: none"> - Assign operating system profiles to repository folders if the PowerCenter Integration Service uses operating system profiles.* - Change the owner of folders and global objects.* - Configure folder and global object permissions.* - Connect to the PowerCenter Integration Service from the PowerCenter Client when running the PowerCenter Integration Service in safe mode. - Delete a PowerCenter Integration Service from the Navigator of the Workflow Manager. - Delete folders and global objects.* - Designate folders to be shared.* - Edit the name and description of folders.* <p>*The PowerCenter repository folder owner or global object owner can also complete these tasks.</p>

Service	Tasks
Domain	<ul style="list-style-type: none"> - Configure domain properties. - Grant permission on the domain - Manage and purge log events. - Receive domain alerts. - View user activity log events.

Service	Tasks
Domain	<ul style="list-style-type: none"> - Configure domain properties. - Grant permission on the domain - Manage and purge log events. - Receive domain alerts. - View user activity log events.

Custom Roles

A custom role is a role that you can edit or delete.

By default, the Administrator tool includes the following custom roles:

- Analyst Service custom role
- Metadata Manager Service custom roles
- Operator custom role
- PowerCenter Repository Service custom roles
- Test Data Manager Service custom roles

You can edit the privileges for these roles, or delete the roles. You can also create your own custom roles.

Creating Custom Roles

When you create a custom role, you assign privileges to the role for the domain or for an application service type. A role can include privileges for one or more services.

1. In the Administrator tool, click the Security tab.
2. On the Security Actions menu, click Create Role.
The Create Role dialog box appears.
3. Enter the following properties for the role:

Property	Description
Name	Name of the role. The role name is case insensitive and cannot exceed 128 characters. It cannot include a tab, newline character, or the following special characters: , + " \ < > ; / * % ? The name can include an ASCII space character except for the first and last character. All other space characters are not allowed.
Description	Description of the role. The description cannot exceed 765 characters or include a tab, newline character, or the following special characters: < > "

4. Click the Privileges tab.
5. Expand the domain or an application service type.
6. Select the privileges to assign to the role for the domain or application service type.
7. Click OK.

Editing Properties for Custom Roles

When you edit a custom role, you can change the description of the role. You cannot change the name of the role.

1. In the Administrator tool, click the Security tab.
2. In the Roles section of the Navigator, select a role.
3. Click Edit.
4. Change the description of the role and click OK.

Editing Privileges Assigned to Custom Roles

You can change the privileges assigned to a custom role for the domain and for each application service type.

1. In the Administrator tool, click the Security tab.
2. In the Roles section of the Navigator, select a role.
3. Click the Privileges tab.
4. Click Edit.
The Edit Roles and Privileges dialog box appears.
5. Expand the domain or an application service type.
6. To assign privileges to the role, select the privileges for the domain or application service type.
7. To remove privileges from the role, clear the privileges for the domain or application service type.
8. Repeat the steps to change the privileges for each service type.
9. Click OK.

Deleting Custom Roles

When you delete a custom role, the custom role and all privileges that it included are removed from any user or group assigned the role.

To delete a custom role, right-click the role in the Roles section of the Navigator and select Delete Role. Confirm that you want to delete the role.

Assigning Privileges and Roles to Users and Groups

You determine the actions that users can perform by assigning the following items to users and groups:

- Privileges. A privilege determines the actions that users can perform in application clients.
- Roles. A role is a collection of privileges. When you assign a role to a user or group, you assign the collection of privileges belonging to the role.

Use the following rules and guidelines when you assign privileges and roles to users and groups:

- You assign privileges and roles to users and groups for the domain and for each application service that is running in the domain.
You cannot assign privileges and roles to users and groups for a Metadata Manager Service or PowerCenter Repository Service in the following situations:
 - The application service is disabled.
 - The PowerCenter Repository Service is running in exclusive mode.
- You can assign different privileges and roles to a user or group for each application service of the same service type.
- A role can include privileges for the domain and multiple application service types. When you assign the role to a user or group for one application service, privileges for that application service type are assigned to the user or group.

If you change the privileges or roles assigned to a user, the changed privileges or roles take effect the next time that the user logs in.

Note: You cannot edit the privileges or roles assigned to the default Administrator user account.

Inherited Privileges

A user or group can inherit privileges from the following objects:

- Group. When you assign privileges to a group, all subgroups and users belonging to the group inherit the privileges.
- Role. When you assign a role to a user, the user inherits the privileges belonging to the role. When you assign a role to a group, the group and all subgroups and users belonging to the group inherit the privileges belonging to the role. The subgroups and users do not inherit the role.

You cannot revoke privileges inherited from a group or role. You can assign additional privileges to a user or group that are not inherited from a group or role.

The Privileges tab for a user or group displays all the roles and privileges assigned to the user or group for the domain and for each application service. Expand the domain or application service to view the roles and privileges assigned for the domain or service. Click the following items to display additional information about the assigned roles and privileges:

- Name of an assigned role. Displays the role details on the details panel.
- Information icon for an assigned role. Highlights all privileges inherited with that role.

Privileges that are inherited from a role or group display an inheritance icon. The tooltip for an inherited privilege displays which role or group the user inherited the privilege from.

Assigning Privileges and Roles to a User or Group by Navigation

1. In the Administrator tool, click the Security tab.
2. In the Navigator, select a user or group.
3. Click the Privileges tab.
4. Click Edit.

The Edit Roles and Privileges dialog box appears.

5. To assign roles, expand the domain or an application service on the Roles tab.
6. To grant roles, select the roles to assign to the user or group for the domain or application service.
You can select any role that includes privileges for the selected domain or application service type.
7. To revoke roles, clear the roles assigned to the user or group.
8. Repeat steps [5](#) through [7](#) to assign roles for another service.
9. To assign privileges, click the Privileges tab.
10. Expand the domain or an application service.
11. To grant privileges, select the privileges to assign to the user or group for the domain or application service.
12. To revoke privileges, clear the privileges assigned to the user or group.
You cannot revoke privileges inherited from a role or group.
13. Repeat steps [10](#) through [12](#) to assign privileges for another service.
14. Click OK.

Viewing Users with Privileges for a Service

You can view all users that have privileges for the domain or an application service.

1. In the Administrator tool, click the Security tab.
2. On the Security Actions menu, click Service User Privileges.
The Services dialog box appears.
3. Select the domain or an application service.
The details panel displays all users that have privileges for the domain or application service.
4. Right-click a user name and click Navigate to Item to navigate to the user.

Troubleshooting Privileges and Roles

I cannot assign privileges or roles to users for an existing Metadata Manager Service or PowerCenter Repository Service.

You cannot assign privileges and roles to users and groups for an existing Metadata Manager Service or PowerCenter Repository Service in the following situations:

- The application service is disabled.
- The PowerCenter Repository Service is running in exclusive mode.

I removed a privilege from a group. Why do some users in the group still have that privilege?

You can use any of the following methods to assign privileges to a user:

- Assign a privilege directly to a user.
- Assign a role to a user.
- Assign a privilege or role to a group that the user belongs to.

If you remove a privilege from a group, users that belong to that group can be directly assigned the privilege or can inherit the privilege from an assigned role.

I am assigned all domain privileges and permission on all domain objects, but I cannot complete all tasks in the Administrator tool.

Some of the Administrator tool tasks are determined by the Administrator role, not by privileges or permissions. You can be assigned all privileges for the domain and granted full permissions on all domain objects. However, you cannot complete the tasks determined by the Administrator role.

I am assigned the Administrator role for an application service, but I cannot configure the application service in the Administrator tool.

When you have the Administrator role for an application service, you are an application client administrator. An application client administrator has full permissions and privileges in an application client.

However, an application client administrator does not have permissions or privileges on the Informatica domain. An application client administrator cannot log in to the Administrator tool to manage the service for the application client for which it has administrator privileges.

To manage an application service in the Administrator tool, you must have the appropriate domain privileges and permissions.

I am assigned the Administrator role for the PowerCenter Repository Service, but I cannot use the Repository Manager to perform an advanced purge of objects or to create reusable metadata extensions.

You must have the Manage Services domain privilege and permission on the PowerCenter Repository Service in the Administrator tool to perform the following actions in the Repository Manager:

- Perform an advanced purge of object versions at the PowerCenter repository level.
- Create, edit, and delete reusable metadata extensions.

My privileges indicate that I should be able to edit objects in an application client, but I cannot edit any metadata.

You might not have the required object permissions in the application client. Even if you have the privilege to perform certain actions, you may also require permission to perform the action on a particular object.

I cannot use pmrep to connect to a new PowerCenter Repository Service running in exclusive mode.

The Service Manager might not have synchronized the list of users and groups in the PowerCenter repository with the list in the domain configuration database. To synchronize the list of users and groups, restart the PowerCenter Repository Service.

I am assigned all privileges in the Folders privilege group for the PowerCenter Repository Service and have read, write, and execute permission on a folder. However, I cannot configure the permissions for the folder.

Only the folder owner or a user assigned the Administrator role for the PowerCenter Repository Service can complete the following folder management tasks:

- Assign operating system profiles to folders if the PowerCenter Integration Service uses operating system profiles. Requires permission on the operating system profile.
- Change the folder owner.
- Configure folder permissions.
- Delete the folder.
- Designate the folder to be shared.
- Edit the folder name and description.

I am assigned the Administrator role for the Metadata Manager Service, but I cannot create or restore the Metadata Manager repository.

To create or restore the Metadata Manager repository, you must be in the default Administrator group. Users in the default Administrator group have more privileges than users that are assigned the Administrator role for an application service.

I am assigned the Load Resources privilege for the Metadata Manager Service, but I get an "insufficient privileges" error when I try to load Business Glossary resources.

To load Business Glossary resources, the Load Resource, Manage Resource, and View Model privileges are required. You also need write permission on any business glossary resource that you want to load.

CHAPTER 10

Permissions

This chapter includes the following topics:

- [Permissions Overview, 184](#)
- [Domain Object Permissions, 186](#)
- [Connection Permissions, 191](#)
- [Application and Application Object Permissions, 194](#)
- [SQL Data Service Permissions, 196](#)
- [Web Service Permissions, 200](#)

Permissions Overview

You manage user security with privileges and permissions. Permissions define the level of access that users and groups have to an object.

Even if a user has the privilege to perform certain actions, the user may also require permission to perform the action on a particular object.

For example, a user has the Manage Services domain privilege and permission on the Development PowerCenter Repository Service, but not on the Production PowerCenter Repository Service. The user can edit or remove the Development PowerCenter Repository Service, but not the Production PowerCenter Repository Service. To manage an application service, a user must have the Manage Services domain privilege and permission on the application service.

You use different tools to configure permissions on the following objects:

You use different tools to configure permissions on the following objects:

Object Type	Tool	Description
Applications and application objects	Administrator tool	You can assign permissions on applications and application objects such as mappings and workflows.
Connection objects	Administrator tool Analyst tool Developer tool	You can assign permissions on connections defined in the Administrator tool, Analyst tool, or Developer tool. These tools share the connection permissions.

Object Type	Tool	Description
Domain objects	Administrator tool	You can assign permissions on the following domain objects: domain, folders, nodes, grids, licenses, application services, and operating system profiles.
Metadata Manager catalog objects	Metadata Manager	You can assign permissions on Metadata Manager folders and catalog objects.
Model repository projects	Analyst tool Developer tool	You can assign permissions on projects defined in the Analyst tool and Developer tool. These tools share project permissions.
PowerCenter repository objects	PowerCenter Client	You can assign permissions on PowerCenter folders, deployment groups, labels, queries, and connection objects.
SQL data service objects	Administrator tool	You can assign permissions on SQL data objects, such as SQL data services, virtual schemas, virtual tables, and virtual stored procedures.
Web service objects	Administrator tool	You can assign permissions on web services or web service operations.

Object Type	Tool	Description
Connection objects	Administrator tool Developer tool	You can assign permissions on connections defined in the Administrator tool or Developer tool. These tools share the connection permissions.
Domain objects	Administrator tool	You can assign permissions on the following domain objects: domain, folders, node, and application services.
Model repository projects	Developer tool	You can assign permissions on projects defined in the Developer tool.

You can use the Administrator tool to configure permissions on a domain object. You can assign permissions on the following domain objects:

- domain
- node
- application services

Types of Permissions

Users and groups can have the following types of permissions in a domain:

Direct permissions

Permissions that are assigned directly to a user or group. When users and groups have permission on an object, they can perform administrative tasks on that object if they also have the appropriate privilege. You can edit direct permissions.

Inherited permissions

Permissions that users inherit. When users have permission on a domain or a folder, they inherit permission on all objects in the domain or the folder. When groups have permission on a domain object,

all subgroups and users belonging to the group inherit permission on the domain object. For example, a domain has a folder named Nodes that contains multiple nodes. If you assign a group permission on the folder, all subgroups and users belonging to the group inherit permission on the folder and on all nodes in the folder.

Permissions that users inherit. When users have permission on a domain, they inherit permission on all objects in the domain. When groups have permission on a domain object, all subgroups and users belonging to the group inherit permission on the domain object.

Permissions that users inherit. When users have permission on a domain, they inherit permission on all objects in the domain. When groups have permission on a domain object, all subgroups and users belonging to the group inherit permission on the domain object.

You cannot revoke inherited permissions. You also cannot revoke permissions from users or groups assigned the Administrator role. The Administrator role bypasses permission checking. Users with the Administrator role can access all objects.

You can deny inherited permissions on some object types. When you deny permissions, you configure exceptions to the permissions that users and groups might already have.

Effective permissions

Superset of all permissions for a user or group. Includes direct permissions and inherited permissions.

When you view permission details, you can view the origin of effective permissions. Permission details display direct permissions assigned to the user or group, direct permissions assigned to parent groups, and permissions inherited from parent objects. In addition, permission details display whether the user or group is assigned the Administrator role which bypasses permission checking.

Permission Search Filters

When you assign permissions, view permission details, or edit permissions for a user or group, you can use search filters to search for a user or group.

When you manage permissions for a user or group, you can use the following search filters:

Security domain

Select the security domain to search for users or groups.

Pattern string

Enter a string to search for users or groups. The Administrator tool returns all names that contain the search string. The string is not case sensitive. For example, the string "DA" can return "iasdaemon," "daphne," and "DA_AdminGroup."

You can also sort the list of users or groups. Right-click a column name to sort the column in ascending or descending order.

Domain Object Permissions

You configure privileges and permissions to manage user security within the domain. Permissions define the level of access a user has to a domain object. To log in to the Administrator tool, a user must have permission on at least one domain object. If a user has permission on an object, but does not have the domain privilege that grants the ability to modify the object type, then the user can only view the object.

For example, if a user has permission on a node, but does not have the Manage Nodes and Grids privilege, the user can view the node properties, but cannot configure, shut down, or remove the node.

You can configure permissions on the following types of domain objects:

Domain Object Type	Description of Permission
Domain	Enables Administrator tool users to access all objects in the domain. When users have permission on a domain, they inherit permission on all objects in the domain.
Folder	Enables Administrator tool users to access all objects in the folder in the Administrator tool. When users have permission on a folder, they inherit permission on all objects in the folder.
Node	Enables Administrator tool users to view and edit the node properties. Without permission, a user cannot use the node when defining an application service or creating a grid.
Grid	Enables Administrator tool users to view and edit the grid properties. Without permission, a user cannot assign the grid to a Data Integration Service or PowerCenter Integration Service.
License	Enables Administrator tool users to view and edit the license properties. Without permission, a user cannot use the license when creating an application service.
Application Service	Enables Administrator tool users to view and edit the application service properties.
Operating System Profile	Enables Informatica developers, analysts, and operators associated with the operating system profile to run mappings, profiles, and workflows. Enables PowerCenter users to run workflows associated with the operating system profile. If the user that runs a workflow does not have permission on the operating system profile assigned to the workflow, the workflow fails.

Domain Object Type	Description of Permission
Domain	Enables Administrator tool users to access all objects in the domain. When users have permission on a domain, they inherit permission on all objects in the domain.
Node	Enables Administrator tool users to view and edit the node properties.
Application Service	Enables Administrator tool users to view and edit the application service properties.
License	Enables Administrator tool users to view and edit the license properties.

Domain Object Type	Description of Permission
Domain	Enables Administrator tool users to access all objects in the domain. When users have permission on a domain, they inherit permission on all objects in the domain.
Node	Enables Administrator tool users to view and edit the node properties.
Application Service	Enables Administrator tool users to view and edit the application service properties.
License	Enables Administrator tool users to view and edit the license properties.

You can use the following methods to manage domain object permissions:

- Manage permissions by domain object. Use the Permissions view of a domain object to assign and edit permissions on the object for multiple users or groups.
- Manage permissions by user or group. Use the Manage Permissions dialog box to assign and edit permissions on domain objects for a specific user or group.

Note: You configure permissions on an operating system profile differently than you configure permissions on other domain objects.

Permissions by Domain Object

Use the **Permissions** view of a domain object to assign, view, and edit permissions on the domain object for multiple users or groups.

Assigning Permissions on a Domain Object

When you assign permissions on a domain object, you grant users and groups access to the object.

1. On the Manage tab, select the **Services and Nodes** view.
2. In the Navigator, select the domain object.
3. In the contents panel, select the **Permissions** view.
4. Click the **Groups** or **Users** tab.
5. Click **Actions > Assign Permission**.

The **Assign Permissions** dialog box displays all users or groups that do not have permission on the object.

6. Enter the filter conditions to search for users and groups, and click the **Filter** button.
7. Select a user or group, and click **Next**.
8. Select **Allow**, and click **Finish**.

Viewing Permission Details on a Domain Object

When you view permission details, you can view the origin of effective permissions.

1. On the Manage tab, select the **Services and Nodes** view.
2. In the Navigator, select the domain object.
3. In the contents panel, select the **Permissions** view.
4. Click the **Groups** or **Users** tab.
5. Enter the filter conditions to search for users and groups, and click the **Filter** button.
6. Select a user or group and click **Actions > View Permission Details**.

The **Permission Details** dialog box appears. The dialog box displays direct permissions assigned to the user or group, direct permissions assigned to parent groups, and permissions inherited from parent objects. In addition, permission details display whether the user or group is assigned the Administrator role which bypasses permission checking.

7. Click **Close**.
8. Or, click **Edit Permissions** to edit direct permissions.

Editing Permissions on a Domain Object

You can edit direct permissions on a domain object for a user or group. You cannot revoke inherited permissions or your own permissions.

Note: If you revoke direct permission on an object, the user or group might still inherit permission from a parent group or object.

1. On the Manage tab, select the **Services and Nodes** view.
2. In the Navigator, select the domain object.
3. In the contents panel, select the **Permissions** view.
4. Click the **Groups** or **Users** tab.
5. Enter the filter conditions to search for users and groups, and click the **Filter** button.
6. Select a user or group and click **Actions > Edit Direct Permissions**.

The **Edit Direct Permissions** dialog box appears.

7. To assign permission on the object, select **Allow**.
8. To revoke permission on the object, select **Revoke**.

You can view whether the permission is directly assigned or inherited by clicking **View Permission Details**.

9. Click **OK**.

Permissions by User or Group

Use the **Manage Permissions** dialog box to view, assign, and edit domain object permissions for a specific user or group.

Viewing Permission Details for a User or Group

When you view permission details, you can view the origin of effective permissions.

1. In the header of Infomatica Administrator, click **Manage > Permissions**.
The **Manage Permissions** dialog box appears.
2. Click the **Groups** or **Users** tab.
3. Enter a string to search for users and groups, and click the **Filter** button.
4. Select a user or group.
5. Select a domain object and click the **View Permission Details** button.

The **Permission Details** dialog box appears. The dialog box displays direct permissions assigned to the user or group, direct permissions assigned to parent groups, and permissions inherited from parent objects. In addition, permission details display whether the user or group is assigned the Administrator role which bypasses permission checking.

6. Click **Close**.
7. Or, click **Edit Permissions** to edit direct permissions.

Assigning and Editing Permissions for a User or Group

When you edit domain object permissions for a user or group, you can assign permissions and edit existing direct permissions. You cannot revoke inherited permissions or your own permissions.

Note: If you revoke direct permission on an object, the user or group might still inherit permission from a parent group or object.

1. In the header of Infomatica Administrator, click **Manage > Permissions**.
The **Manage Permissions** dialog box appears.
2. Click the **Groups** or **Users** tab.
3. Enter a string to search for users and groups and click the **Filter** button.
4. Select a user or group.
5. Select a domain object and click the **Edit Direct Permissions** button.
The **Edit Direct Permissions** dialog box appears.
6. To assign permission on the object, select **Allow**.
7. To revoke permission on the object, select **Revoke**.
You can view whether the permission is directly assigned or inherited by clicking **View Permission Details**.
8. Click **OK**.
9. Click **Close**.

Operating System Profile Permissions

Assign, view, and edit permissions on operating system profiles in the Security page of the Administrator tool.

The Administrator group has permissions on all operating system profiles.

Assigning Permissions on an Operating System Profile

When you assign permissions on an operating system profile, Informatica users run mappings, profiles, and workflows with the operating system profile. PowerCenter users run workflows assigned to the operating system profile.

1. On the **Security** tab, select the **Operating System Profiles** view.
2. Select the operating system profile, and click the **Permissions** tab.
3. Select the **Groups** or **Users** view, and click **Grant Permission**.
The **Assign Users/Groups to Operating System Profile** dialog box displays all users or groups that do not have permission on the operating system profile.
4. Enter the filter conditions to search for users and groups, and click the **Filter** button.
5. Select a user or group, and click **Next**.
6. Select **Allow**, and click **Finish**.

Viewing Permission Details on an Operating System Profile

When you view permission details, you can view the origin of effective permissions.

1. On the **Security** tab, select the **Operating System Profiles** view.
2. Select the operating system profile, and click the **Permissions** tab.

3. Select the **Groups** or **Users** view.
4. Enter the filter conditions to search for users and groups, and click the **Filter** button.
5. Select a user or group and click **View Permission Details**.

The **Permission Details** dialog box appears. The dialog box displays direct permissions assigned to the user or group, direct permissions assigned to parent groups, and permissions inherited from parent objects. In addition, permission details display whether the user or group is assigned the Administrator role which bypasses permission checking.

6. Click **Close**.
7. Or, click **Edit Permissions** to edit direct permissions.

Editing Permissions on an Operating System Profile

You can edit direct permissions on an operating system profile for a user or group. You cannot revoke inherited permissions or your own permissions.

Note: If you revoke direct permission on an object, the user or group might still inherit permission from a parent group or object.

1. On the **Security** tab, select the **Operating System Profiles** view.
2. Select the operating system profile, and click the **Permissions** tab.
3. Select the **Groups** or **Users** view.
4. Enter the filter conditions to search for users and groups, and click the **Filter** button.
5. Select a user or group and click **Edit Direct Permissions**.

The **Edit Direct Permissions** dialog box appears.

6. To assign permission on the operating system profile, select **Allow**.
7. To revoke permission on the operating system profile, select **Revoke**.

You can view whether the permission is directly assigned or inherited by clicking **View Permission Details**.

8. Click **OK**.

Connection Permissions

Permissions control the level of access that a user or group has on the connection.

You can configure permissions on a connection in the Analyst tool, Developer tool, or Administrator tool.

You can configure permissions on a connection in the Developer tool or Administrator tool.

Any connection permission that is assigned to a user or group in one tool also applies in other tools. For example, you grant GroupA permission on ConnectionA in the Developer tool. GroupA has permission on ConnectionA in the Analyst tool and Administrator tool also.

Any connection permission that is assigned to a user or group in one tool also applies in other tools. For example, you grant GroupA permission on ConnectionA in the Developer tool. GroupA has permission on ConnectionA in the Administrator tool also.

The following Informatica components use the connection permissions:

- Administrator tool. Enforces read, write, and execute permissions on connections.

- Analyst tool. Enforces read, write, and execute permissions on connections.
- Informatica command line interface. Enforces read, write, and grant permissions on connections.
- Developer tool. Enforces read, write, and execute permissions on connections.
For SQL data services, the Developer tool does not enforce connection permissions. Instead, it enforces column-level and pass-through security to restrict access to data.
- Data Integration Service. Enforces execute permissions when a user tries to preview data or run a mapping, scorecard, or profile.
- Data Integration Service. Enforces execute permissions when a user tries to preview data or run a mapping, or profile.

Note: You cannot assign permissions on the following connections: profiling warehouse, data object cache database, or Model repository.

Types of Connection Permissions

You can assign different permission types to users to perform the following actions:

Action	Permission Types
View all connection metadata, except passwords, such as connection name, type, description, connection strings, and user names.	Read
Edit all connection metadata, including passwords. Delete the connection. Users with Write permission inherit Read permission.	Write
Access the physical data in the underlying data source defined by the connection. Users can preview data, run a mapping, run a mapping in a workflow Mapping task, run a scorecard, or run a profile that uses the connection. Access the physical data in the underlying data source defined by the connection. Users can preview data, run a mapping, run a mapping in a workflow Mapping task, or run a profile that uses the connection.	Execute
Grant and revoke permissions on connections.	Grant

Default Connection Permissions

The domain administrator has all permissions on all connections. The user that creates a connection has read, write, execute, and grant permission on the connection. By default, all users have permission to perform the following actions on connections:

- View basic connection metadata, such as connection name, type, and description.
- Use the connection in mappings in the Developer tool.
- Create profiles in the Analyst tool on objects in the connection.

Assigning Permissions on a Connection

When you assign permissions on a connection, you define the level of access a user or group has to the connection.

1. On the Manage tab, select the **Connections** view.

2. In the Navigator, select the connection.
3. In the contents panel, select the **Permissions** view.
4. Click the **Groups** or **Users** tab.
5. Click **Actions > Assign Permission**.

The **Assign Permissions** dialog box displays all users or groups that do not have permission on the connection.

6. Enter the filter conditions to search for users and groups, and click the **Filter** button.
7. Select a user or group, and click **Next**.
8. Select **Allow** for each permission type that you want to assign.
9. Click **Finish**.

Viewing Permission Details on a Connection

When you view permission details, you can view the origin of effective permissions.

1. On the Manage tab, select the **Connections** view.
2. In the Navigator, select the connection.
3. In the contents panel, select the **Permissions** view.
4. Click the **Groups** or **Users** tab.
5. Enter the filter conditions to search for users and groups, and click the **Filter** button.
6. Select a user or group and click **Actions > View Permission Details**.

The **View Permission Details** dialog box appears. The dialog box displays direct permissions assigned to the user or group and direct permissions assigned to parent groups. In addition, permission details display whether the user or group is assigned the Administrator role which bypasses the permission check.

7. Click **Close**.
8. Or, click **Edit Permissions** to edit direct permissions.

Editing Permissions on a Connection

You can edit direct permissions on a connection for a user or group. You cannot revoke inherited permissions or your own permissions.

Note: If you revoke direct permission on an object, the user or group might still inherit permission from a parent group or object.

1. On the Manage tab, select the **Connections** view.
2. In the Navigator, select the connection.
3. In the contents panel, select the **Permissions** view.
4. Click the **Groups** or **Users** tab.
5. Enter the filter conditions to search for users and groups, and click the **Filter** button.
6. Select a user or group and click **Actions > Edit Direct Permissions**.

The **Edit Direct Permissions** dialog box appears.

7. Choose to allow or revoke permissions.
 - Select **Allow** to assign a permission.

- Clear **Allow** to revoke a single permission.
- Select **Revoke** to revoke all permissions.

You can view whether the permission is directly assigned or inherited by clicking **View Permission Details**.

8. Click **OK**.

Application and Application Object Permissions

Permissions control the level of access that a user or group has on applications and application objects such as mappings and workflows.

You can configure application and application object permissions in the Administrator tool or from the command line.

Types of Application and Application Object Permissions

You can assign view, grant, and execute permissions to users and groups.

You can assign the following permissions to users and groups:

View permission

View applications and application objects.

Grant permission

Grant and revoke permissions on the applications and application objects.

Execute permission

Run applications and application objects.

Note: To perform application operations such as start, stop, or back up in the Administrator tool or from the command line, the user must have execute permission and the Manage Applications privilege on the application.

Assigning Permissions on an Application or Application Object

When you assign permissions on an application or application object, you define the level of access a user or group has to the application or the application object.

1. On the Manage tab, select the **Services and Nodes** view.
2. In the Navigator, select a Data Integration Service.
3. In the contents panel, select the **Applications** view.
4. Select an application, a mapping, or a workflow.
5. In the details panel, select the **Group Permissions** or **User Permissions** view.
6. Click the **Assign Permission** button.

The **Assign Permissions** dialog box displays all users or groups that do not have permission on the application or application object.

7. Enter the filter conditions to search for users and groups, and click the **Filter** button.
8. Select a user or group, and click **Next**.

9. Select **Allow** for each permission type that you want to assign.
10. Click **Finish**.

Viewing Permission Details on an Application or Application Object

When you view permission details, you can view the origin of effective permissions.

1. On the Manage tab, select the **Services and Nodes** view.
2. In the Navigator, select a Data Integration Service.
3. In the contents panel, select the **Applications** view.
4. Select the application, mapping, or workflow.
5. In the details panel, select the **Group Permissions** or **User Permissions** view.
6. Enter the filter conditions to search for users and groups, and click the **Filter** button.
7. Select a user or group and click the **View Permission Details** button.

The **Permission Details** dialog box appears. The dialog box displays direct permissions assigned to the user or group, direct permissions assigned to parent groups, and permissions inherited from parent objects. In addition, permission details display whether the user or group is assigned the Administrator role which bypasses permission checking.

8. Click **Close**.
9. Or, click **Edit Permissions** to edit direct permissions.

Editing Permissions on an Application or Application Object

You can edit direct permissions on an application or application object for a user or group. You cannot revoke inherited permissions or your own permissions.

Note: If you revoke direct permission on an object, the user or group might still inherit permission from a parent group or object.

1. On the Manage tab, select the **Services and Nodes** view.
2. In the Navigator, select a Data Integration Service.
3. In the contents panel, select the **Applications** view.
4. Select the application or application object.
5. In the details panel, select the **Group Permissions** or **User Permissions** view.
6. Enter the filter conditions to search for users and groups, and click the **Filter** button.
7. Select a user or group and click the **Edit Direct Permissions** button.

The **Edit Direct Permissions** dialog box appears.

8. Choose to allow or revoke permissions.
 - Select **Allow** to assign a permission.
 - Clear **Allow** to revoke a single permission.
 - Select **Revoke** to revoke all permissions.

You can view whether the permission is directly assigned or inherited by clicking **View Permission Details**.

9. Click **OK**.

Denying Permissions on an Application or Application Object

You can explicitly deny permissions on application and application objects. When you deny a permission, you are applying an exception to the effective permission.

SQL Data Service Permissions

End users can connect to an SQL data service through a JDBC or ODBC client tool. After connecting, users can run SQL queries against virtual tables in an SQL data service, or users can run a virtual stored procedure in an SQL data service. Permissions control the level of access that a user has to an SQL data service.

You can assign permissions to users and groups on the following SQL data service objects:

- SQL data service
- Virtual table
- Virtual stored procedure

When you assign permissions on an SQL data service object, the user or group inherits the same permissions on all objects that belong to the SQL data service object. For example, you assign a user select permission on an SQL data service. The user inherits select permission on all virtual tables in the SQL data service.

You can deny permissions to users and groups on some SQL data service objects. When you deny permissions, you configure exceptions to the permissions that users and groups might already have. For example, you cannot assign permissions to a column in a virtual table, but you can deny a user from running an SQL SELECT statement that includes the column.

Types of SQL Data Service Permissions

You can assign the following permissions to users and groups:

- Grant permission. Users can grant and revoke permissions on the SQL data service objects using the Administrator tool or using the *infacmd* command line program.
- Execute permission. Users can run virtual stored procedures in the SQL data service using a JDBC or ODBC client tool.
- Select permission. Users can run SQL SELECT statements on virtual tables in the SQL data service using a JDBC or ODBC client tool.

Some permissions are not applicable for all SQL data service objects.

The following table describes the permissions for each SQL data service object:

Object	Grant Permission	Execute Permission	Select Permission
SQL data service	Grant and revoke permission on the SQL data service and all objects within the SQL data service.	Run all virtual stored procedures in the SQL data service.	Run SQL SELECT statements on all virtual tables in the SQL data service.
Virtual table	Grant and revoke permission on the virtual table.	-	Run SQL SELECT statements on the virtual table.
Virtual stored procedure	Grant and revoke permission on the virtual stored procedure.	Run the virtual stored procedure.	-

Assigning Permissions on an SQL Data Service

When you assign permissions on an SQL data service object, you define the level of access a user or group has to the object.

1. On the Manage tab, select the **Services and Nodes** view.
2. In the Navigator, select a Data Integration Service.
3. In the contents panel, select the **Applications** view.
4. Select the SQL data service object.
5. In the details panel, select the **Group Permissions** or **User Permissions** view.
6. Click the **Assign Permission** button.

The **Assign Permissions** dialog box displays all users or groups that do not have permission on the SQL data service object.

7. Enter the filter conditions to search for users and groups, and click the **Filter** button.
8. Select a user or group, and click **Next**.
9. Select **Allow** for each permission type that you want to assign.
10. Click **Finish**.

Viewing Permission Details on an SQL Data Service

When you view permission details, you can view the origin of effective permissions.

1. On the Manage tab, select the **Services and Nodes** view.
2. In the Navigator, select a Data Integration Service.
3. In the contents panel, select the **Applications** view.
4. Select the SQL data service object.
5. In the details panel, select the **Group Permissions** or **User Permissions** view.
6. Enter the filter conditions to search for users and groups, and click the **Filter** button.
7. Select a user or group and click the **View Permission Details** button.

The **Permission Details** dialog box appears. The dialog box displays direct permissions assigned to the user or group, direct permissions assigned to parent groups, and permissions inherited from parent objects. In addition, permission details display whether the user or group is assigned the Administrator role which bypasses permission checking.

8. Click **Close**.
9. Or, click **Edit Permissions** to edit direct permissions.

Editing Permissions on an SQL Data Service

You can edit direct permissions on an SQL data service for a user or group. You cannot revoke inherited permissions or your own permissions.

Note: If you revoke direct permission on an object, the user or group might still inherit permission from a parent group or object.

1. On the Manage tab, select the **Services and Nodes** view.
2. In the Navigator, select a Data Integration Service.
3. In the contents panel, select the **Applications** view.

4. Select the SQL data service object.
5. In the details panel, select the **Group Permissions** or **User Permissions** view.
6. Enter the filter conditions to search for users and groups, and click the **Filter** button.
7. Select a user or group and click the **Edit Direct Permissions** button.
The **Edit Direct Permissions** dialog box appears.
8. Choose to allow or revoke permissions.
 - Select **Allow** to assign a permission.
 - Clear **Allow** to revoke a single permission.
 - Select **Revoke** to revoke all permissions.You can view whether the permission is directly assigned or inherited by clicking **View Permission Details**.
9. Click **OK**.

Denying Permissions on an SQL Data Service

You can explicitly deny permissions on some SQL data service objects. When you deny a permission on an object in an SQL data service, you are applying an exception to the effective permission.

To deny permissions use one of the following `infacmd` commands:

- `infacmd sql SetStoredProcedurePermissions`. Denies Execute or Grant permissions at the stored procedure level.
- `infacmd sql SetTablePermissions`. Denies Select and Grant permissions at the virtual table level.
- `infacmd sql SetColumnPermissions`. Denies Select permission at the column level.

Each command has options to apply permissions (`-ap`) and deny permissions (`-dp`). The `SetColumnPermissions` command does not include the apply permissions option.

Note: You cannot deny permissions from the Administrator tool.

The Data Integration Service verifies permissions before running SQL queries and stored procedures against the virtual database. The Data Integration Service validates the permissions for users or groups starting at the SQL data service level. When permissions apply to a parent object in an SQL data service, the child objects inherit the permission. The Data Integration Service checks for denied permissions at the column level.

Column Level Security

An administrator can deny access to columns in a virtual table of an SQL data object. The administrator can configure the Data Integration Service behavior for queries against a restricted column.

The following results might occur when the user queries a column that the user does not have permissions for:

- The query returns a substitute value instead of the data. The query returns a substitute value in each row that it returns. The substitute value replaces the column value through the query. If the query includes filters or joins, the results substitute appears in the results.
- The query fails with an insufficient permission error.

For more information about configuring security for SQL data services, see the Informatica How-To Library article "How to Configure Security for SQL Data Services":

https://kb.informatica.com/h2l/HowTo%20Library/1/0266_ConfiguringSecurityForSQLDataServices.pdf.

Restricted Columns

When you configure column level security, set a column option that determines what happens when a user selects the restricted column in a query. You can substitute the restricted data with a default value. Or, you can fail the query if a user selects the restricted column.

For example, an Administrator denies a user access to the salary column in the Employee table. The Administrator configures a substitute value of 100,000 for the salary column. When the user selects the salary column in an SQL query, the Data Integration Service returns 100,000 for the salary in each row.

Run the `infacmd sql UpdateColumnOptions` command to configure the column options. You cannot set column options in the Administrator tool.

When you run `infacmd sql UpdateColumnOptions`, enter the following options:

ColumnOptions.DenyWith=option

Determines whether to substitute the restricted column value or to fail the query. If you substitute the column value, you can choose to substitute the value with NULL or with a constant value. Enter one of the following options:

- **ERROR.** Fails the query and returns an error when an SQL query selects a restricted column.
- **NULL.** Returns null values for a restricted column in each row.
- **VALUE.** Returns a constant value in place of the restricted column in each row. Configure the constant value in the `ColumnOptions.InsufficientPermissionValue` option.

ColumnOptions.InsufficientPermissionValue=value

Substitutes the restricted column value with a constant. The default is an empty string. If the Data Integration Service substitutes the column with an empty string, but the column is a number or a date, the query returns errors. If you do not configure a value for the `DenyWith` option, the Data Integration Service ignores the `InsufficientPermissionValue` option.

To configure a substitute value for a column, enter the command with the following syntax:

```
infacmd sql UpdateColumnOptions -dn empDomain -sn DISService -un Administrator -pd
Adminpass -sqlds employee_APP.employees_SQL -t Employee -c Salary -o
ColumnOptions.DenyWith=VALUE ColumnOptions.InsufficientPermissionValue=100000
```

If you do not configure either option for a restricted column, default is not to fail the query. The query runs and the Data Integration Service substitutes the column value with NULL.

Adding Column Level Security

Configure column level security with the `infacmd sql SetColumnPermissions` command. You cannot set column level security from the Administrator tool.

An Employee table contains `FirstName`, `LastName`, `Dept`, and `Salary` columns. You enable a user to access the Employee table but restrict the user from accessing the salary column.

To restrict the user from the salary column, disable the Data Integration Service and enter an `infacmd` similar to the following command:

```
infacmd sql SetColumnPermissions -dn empDomain -sn DISService -un Administrator -pd
Adminpass -sqlds employee_APP.employees -t Employee -c Salary gun -Tom -dp SQL_Select
```

The following SQL statements return NULL in the salary column:

```
Select * from Employee
Select LastName, Salary from Employee
```

The default behavior is to return null values.

Web Service Permissions

End users can send web service requests and receive web service responses through a web service client. Permissions control the level of access that a user has to a web service.

You can assign permissions to users and groups on the following web service objects:

- Web service
- REST web service resource
- SOAP web service operation

When you assign permissions on a web service object, the user or group inherits the same permissions on all objects that belong to the web service object. For example, you assign a user execute permission on a web service. The user inherits execute permission on web service operations in the web service.

You can deny permissions to users and groups on a web service operation. When you deny permissions, you configure exceptions to the permissions that users and groups might already have. For example, a user has execute permissions on a web service which has three operations. You can deny a user from running one web service operation that belongs to the web service.

Types of Web Service Permissions

An administrator assigns web service permissions to the following types of users and groups:

- Web service consumer. A native domain user that sends a request to the web service and receives a response from the web service. The user must have execute permission on the web service.
- Web service administrator. A user that can log into the Administrator, edit the web service properties, and grant permissions to other users.
- Web service operator. A user that can log into the Administrator, monitor a web service, and start or stop a web service.

An administrator can assign the following permissions to users and groups:

- Grant permission. Users can manage permissions on the web service objects using the Administrator tool or using the *infacmd* command line program.
- Execute permission. Users can send web service requests and receive web service responses.

The following table describes the permissions for each SOAP web service object:

Object	Grant Permission	Execute Permission
SOAP Web service	Grant and revoke permission on the web service and all web service operations within the web service.	Send web service requests and receive web service responses from all web service operations within the web service.
SOAP Web service operation	Grant, revoke, and deny permission on the web service operation.	Send web service requests and receive web service responses from the web service operation.

The following table describes the permissions for each REST web service object:

Object	Grant Permission	Execute Permission
REST web service	Grant and revoke permission on the REST web service and all web service resources within the web service.	Send web service requests and receive web service responses from all web service resources in the REST web service.
REST resource	Grant, revoke, and deny permission the REST web service resource.	Send web service requests and receive web service responses from the REST web service resource.

Assigning Permissions on a Web Service

When you assign permissions on a web service object, you define the level of access a user or group has to the object.

1. On the Manage tab, select the **Services and Nodes** view.
2. In the Navigator, select a Data Integration Service.
3. In the contents panel, select the **Applications** view.
4. Select the web service object.
5. In the details panel, select the **Group Permissions** or **User Permissions** view.
6. Click the **Assign Permission** button.

The **Assign Permissions** dialog box displays all users or groups that do not have permission on the SQL data service object.

7. Enter the filter conditions to search for users and groups, and click the **Filter** button.
8. Select a user or group, and click **Next**.
9. Select **Allow** for each permission type that you want to assign.
10. Click **Finish**.

Viewing Permission Details on a Web Service

When you view permission details, you can view the origin of effective permissions.

1. On the Manage tab, select the **Services and Nodes** view.
2. In the Navigator, select a Data Integration Service.
3. In the contents panel, select the **Applications** view.
4. Select the web service object.
5. In the details panel, select the **Group Permissions** or **User Permissions** view.
6. Enter the filter conditions to search for users and groups, and click the **Filter** button.
7. Select a user or group and click the **View Permission Details** button.

The **Permission Details** dialog box appears. The dialog box displays direct permissions assigned to the user or group, direct permissions assigned to parent groups, and permissions inherited from parent objects. In addition, permission details display whether the user or group is assigned the Administrator role which bypasses permission checking.

8. Click **Close**.
9. Or, click **Edit Permissions** to edit direct permissions.

Editing Permissions on a Web Service

You can edit direct permissions on a web service for a user or group. When you edit permissions on a web service object, you can deny permissions on the object. You cannot revoke inherited permissions or your own permissions.

Note: If you revoke direct permission on an object, the user or group might still inherit permission from a parent group or object.

1. On the Manage tab, select the **Services and Nodes** view.
2. In the Navigator, select a Data Integration Service.
3. In the contents panel, select the **Applications** view.
4. Select the web service object.
5. In the details panel, select the **Group Permissions** or **User Permissions** view.
6. Enter the filter conditions to search for users and groups, and click the **Filter** button.
7. Select a user or group and click the **Edit Direct Permissions** button.

The **Edit Direct Permissions** dialog box appears.

8. Choose to allow or revoke permissions.
 - Select **Allow** to assign a permission.
 - Select **Deny** to deny a permission on a web service object.
 - Clear **Allow** to revoke a single permission.
 - Select **Revoke** to revoke all permissions.

You can view whether the permission is directly assigned or inherited by clicking **View Permission Details**.

9. Click **OK**.

CHAPTER 11

Audit Reports

This chapter includes the following topics:

- [Audit Reports Overview, 203](#)
- [User Personal Information, 204](#)
- [User Group Association, 204](#)
- [Privileges, 205](#)
- [Roles Association, 206](#)
- [Domain Object Permission, 206](#)
- [Selecting Users for an Audit Report, 207](#)
- [Selecting Groups for an Audit Report , 207](#)
- [Selecting Roles for an Audit Report, 208](#)

Audit Reports Overview

Use the audit reports to view information about users and groups in the Informatica domain and the privileges and permissions assigned to them.

You can generate the following audit reports:

User Personal Information

Displays information about the user accounts in the domain, including the user status. You can select the users or groups for which you want to generate the report.

User Group Association

Displays information about users and the groups to which they belong. You can select the users or groups for which you want to generate the report.

Privileges

Displays information about privileges assigned to the users and groups in the domain. You can select the users or groups for which you want to generate the report.

Roles

Displays information about the roles assigned the users and groups in the domain. You can select the roles for which you want to generate the report.

Domain Object Permissions

Displays information about the domain objects for which users and groups have permission. You can select the users or groups for which you want to generate the report.

You can generate the audit reports in different formats, including CSV, text, or PDF files. You can also view the report on the screen.

You can generate the audit reports from the Administrator tool or from the command line. To run the audit reports from the command line, run the `infacmd aud` command line program.

User Personal Information

The User Personal Information report displays the contact information and status of user accounts in the domain.

If you run the report for groups, the report organizes the list of users by group and displays the group name and security domain for each group. The report displays nested groups separately.

The User Personal Information report displays the following information:

Login Name

Login name for the user account.

Full Name

Full name for the user account.

Security Domain

Security domain to which the user belongs.

Description

Description of the user account.

Email ID

Email address for the user account.

Phone

Telephone number for the user account.

Account Locked

Indicates whether the account is locked or not. The report displays Yes if the account is locked and No if the account is not locked.

Account Disabled

Indicates whether the account is disabled or not. The report displays Yes if the account is disabled and No if the account is enabled.

User Group Association

The User Group Association report displays information about users and their associated groups.

If you run the report for users, the report displays the list of users and the groups to which they belong.

The User Group Association report displays the following information:

Login Name

Login name for the user account.

Full Name

Full name for the user account.

Security Domain

Security domain to which the user account belongs.

Group Name

Name of the group to which the user belongs.

Group Path

If the group is a single group, the group path shows the group name. If the group is a nested group, the group path shows position of the group within the hierarchy of the nested groups.

Group Security Domain

Security domain for the group to which the user belongs.

If you run the report for groups, the report organizes the list of users by group and displays the group name and security domain for each group. The report displays nested groups separately. For each group, the report shows the list of users and child groups that belong to the group.

The User Group Association report displays the following information for the users that belong to the group:

Login Name

Login name for the user account.

Full Name

Full name for the user account.

Security Domain

Security domain to which the user account belongs.

The User Group Association report displays the following information for the child groups that belong to the group:

Group Name

Name of the group.

Security Domain

Security domain to which the group belongs.

Group Path

If the group is a single group, the group path shows the group name. If the group is a nested group, the group path shows position of the group within the hierarchy of the nested groups.

Privileges

The Privileges report displays the users and groups and the privileges assigned to the users and groups.

If you run the report for users, the report shows the list of users and the privileges assigned to each user. If you run the report for groups, the report shows the list of groups and the privileges assigned to each group.

The Privileges report displays the following information:

Privilege Name

Name of the privilege.

Privilege Path

The hierarchy of the privilege group that contains the privilege.

Object Name

Name of the object on which the privilege is allowed.

Object Type

Type of the object on which the privilege is allowed.

Roles Association

The Roles Association report displays a list of roles and the users and groups to which the roles are assigned.

The Roles Association report displays the following information:

Login Name

Login name for the user account to which the role is assigned. Displays for the list of users.

Full Name

Full name for the user account to which the role is assigned. Displays for the list of users.

Group Name

Name of the group to which the role is assigned. Displays for the list of groups.

Security Domain

Security domain to which the user or group belongs.

Object Name

Name of the object on which the set of privileges in the role are allowed.

Object Type

Type of the object on which the set of privileges in the role are allowed.

Domain Object Permission

The Domain Object Permission report displays the users and groups and the objects to which the users and groups have permission.

If you run the report for users, the report shows the list of users and the objects to which the users have permissions. If you run the report for groups, the report shows the list of groups and the objects to which the groups have permissions.

The Domain Object Permission report displays the following information:

Object Name

Name of the object to which the user or group has permission.

Object Type

Type of the object to which the user or group has permission.

Object Path

Location of the object in the repository.

Selecting Users for an Audit Report

You can generate an audit report for multiple users.

1. In the Administrator tool, click **Security > Audit Reports**.
2. From the **Select Report Type** list, select the type of audit report that you want to run.
3. From the **Generate Report For** list, select **Users** and click **Go**.

The **Select Users** dialog box appears. By default, the **Users** icon is selected and the list of all available users display. The list shows the full name of the user and the security domain to which the user belongs.

4. From the **Available Users** list, select the users for which you want to run the report.

Use the Shift key or Ctrl key to select multiple users.

5. To select users by group, click the **Groups** icon.

The **Available Groups** list displays all groups in the domain and the **Members** list displays the users who are members of the groups. From the **Members** list, select the users for which you want to run the report. You can select users from multiple groups.

6. Click **Add**.

To run the report for all users, click the **Users** icon and then click **Add All** without selecting a user.

To run the report for all users in a group, click the **Groups** icon. Select a group and click **Add All** without selecting a user from the **Members** list.

The selected users move to the **Selected Users** list.

7. From the **Report Output Format** list, select the format in which you want to view the report.

By default, the report displays on the screen.

You can also view an audit report in one of the following formats:

- Text. Generates the audit report as a text file with values listed in columns.
- CSV. Generates the audit report as a text file with values separated by commas.
- PDF. Generates the audit report in .pdf format. You must install Acrobat Reader to view the report.

8. Click **Generate Report**.

Selecting Groups for an Audit Report

You can run audit reports for multiple groups.

1. In the Administrator tool, click **Security > Audit Reports**.
2. From the **Select Report Type** list, select the type of audit report that you want to run.
3. From the **Generate Report For** list, select **Groups** and click **Go**.

The **Select Groups** dialog box appears. The list of groups are organized by security domain.

4. From the **Available Groups** list, select the groups for which you want to run the report.
Use the Shift key or Ctrl key to select multiple groups.
5. Click **Add**.
To run the report for all groups, do not select a group and click **Add All**.
The selected groups move to the **Selected Groups** list.
6. From the **Report Output Format** list, select the format in which you want to view the report.
By default, the reports displays on the screen.
You can also run an audit report in one of the following formats:
 - Text. Generates the audit report as a text file with values listed in columns.
 - CSV. Generates the audit report as a text file with values separated by commas.
 - PDF. Generates the audit report in .pdf format. You must install Acrobat Reader to view the report.
7. Click **Generate Report**.

Selecting Roles for an Audit Report

When you run the Roles Association report, you must select the roles for which you want to run the report.

1. In the Administrator tool, click **Security > Audit Reports**.
2. From the **Select Report Type** list, select the **Roles Association** report.
3. From the **Generate Report For** list, select **Roles** and click **Go**.
The **Select Roles** dialog box appears. The list of system-defined roles display separately from the list of custom roles.
4. From the **Available Roles** list, select the roles for which you want to run the report.
Use the Shift key or Ctrl key to select multiple roles.
5. Click **Add**.
To run the report for all roles, do not select a role and click **Add All**.
The selected roles move to the **Selected Roles** list.
6. From the **Report Output Format** list, select the format in which you want to view the report.
By default, the reports displays on the screen.
You can also run an audit report in one of the following formats:
 - Text. Generates the audit report as a text file with values listed in columns.
 - CSV. Generates the audit report as a text file with values separated by commas.
 - PDF. Generates the audit report in .pdf format. You must install Acrobat Reader to view the report.
7. Click **Generate Report**.

APPENDIX A

Command Line Privileges and Permissions

This appendix includes the following topics:

- [infacmd as Commands, 209](#)
- [infacmd dis Commands, 210](#)
- [infacmd es commands, 211](#)
- [infacmd ipc Commands, 211](#)
- [infacmd isp Commands, 212](#)
- [infacmd mrs Commands, 222](#)
- [infacmd ms Commands, 225](#)
- [infacmd oie Commands, 225](#)
- [infacmd ps Commands, 225](#)
- [infacmd pwx Commands, 226](#)
- [infacmd rms Commands, 227](#)
- [infacmd rtm Commands, 228](#)
- [infacmd sch commands, 228](#)
- [infacmd sql Commands, 229](#)
- [infacmd wfs Commands, 230](#)
- [pmcmd Commands, 230](#)
- [pmrep Commands, 232](#)

infacmd as Commands

To run *infacmd as* commands, users must have one of the listed sets of domain privileges, Analyst Service privileges, and domain object permissions.

The following table lists the required privileges and permissions for *infacmd as* commands:

infacmd as Command	Privilege Group	Privilege Name	Permission On...
CreateAuditTables	Domain Administration	Manage Service	Domain or node where Analyst Service runs
CreateService	Domain Administration	Manage Service	Domain or node where Analyst Service runs
DeleteAuditTables	Domain Administration	Manage Service	Domain or node where Analyst Service runs
ListServiceOptions	-	-	Analyst Service
ListServiceProcessOptions	-	-	Analyst Service
UpdateServiceOptions	Domain Administration	Manage Service	Domain or node where Analyst Service runs
UpdateServiceProcessOptions	Domain Administration	Manage Service	Domain or node where Analyst Service runs

infacmd dis Commands

To run *infacmd dis* commands, users must have one of the listed sets of domain privileges, Data Integration Service privileges, and domain object permissions.

The following table lists the required privileges and permissions for *infacmd dis* commands:

infacmd dis Command	Privilege Group	Privilege Name	Permission On...
BackupApplication	Application Administration	Manage Applications	Application
CancelDataObjectCacheRefresh	-	-	-
CreateService	Domain Administration	Manage Services	Domain or node where Data Integration Service runs
DeployApplication	Application Administration	Manage Applications	Application
ListApplicationObjects	-	-	-
ListApplications	-	-	-
ListComputeOptions	Domain Administration	Manage Services	Data Integration Service
ListDataObjectOptions	-	-	-
ListServiceOptions	Domain Administration	Manage Services	Data Integration Service

infacmd dis Command	Privilege Group	Privilege Name	Permission On...
ListServiceProcessOptions	Domain Administration	Manage Services	Data Integration Service
PurgeDataObjectCache	-	-	-
RefreshDataObjectCache	-	-	-
RenameApplication	Application Administration	Manage Applications	Application
RestoreApplication	Application Administration	Manage Applications	Application
StartApplication	Application Administration	Manage Applications	Application
StopApplication	Application Administration	Manage Applications	Application
stopBlazeService	Application Administration	Manage Applications	Application
UndeployApplication	Application Administration	Manage Applications	Application
UpdateApplication	Application Administration	Manage Applications	Application
UpdateApplicationOptions	Application Administration	Manage Applications	Application
UpdateDataObjectOptions	Application Administration	Manage Applications	-
UpdateComputeOptions	Domain Administration	Manage Services	Data Integration Service
UpdateServiceOptions	Domain Administration	Manage Services	Data Integration Service
UpdateServiceProcessOptions	Domain Administration	Manage Services	Data Integration Service

infacmd es commands

Users must be assigned the Administrator role for the domain to run the following infacmd es commands:

- ListServiceOptions
- UpdateServiceOptions
- UpdateSMTPOptions

infacmd ipc Commands

To run *infacmd ipc* commands, users must have one of the listed Model repository object permissions.

The following table lists the required privileges and permissions for *infacmd ipc* commands:

infacmd ipc Command	Privilege Group	Privilege Name	Permission On...
ExportToPC	-	-	Read on the folder that creates reference tables to be exported
genReuseReportFromPC	Tools	Access Repository Manager	-

infacmd isp Commands

To run *infacmd isp* commands, users must have one of the listed sets of domain privileges, service privileges, domain object permissions, and connection permissions.

Users must be assigned the Administrator role for the domain to run the following commands:

- AddDomainLink
- AssignGroupPermission (on domain)
- AssignGroupPermission (on operating system profiles)
- AddServiceLevel
- AssignUserPermission (on domain)
- AssignUserPermission (on operating system profiles)
- CreateConnection
- CreateOSProfile
- PurgeLog
- RemoveDomainLink
- RemoveOSProfile
- RemoveServiceLevel
- SwitchToGatewayNode
- SwitchToWorkerNode
- UpdateDomainOptions
- UpdateGatewayInfo
- UpdateServiceLevel
- UpdateSMTPOptions

Users must be assigned the Administrator role for the domain to run the UpdateGatewayInfo command.

The following table lists the required privileges and permissions for *infacmd isp* commands:

infacmd isp Command	Privilege Group	Privilege Name	Permission On
GetNodeName	-	-	Node
UpdateGatewayInfo	-	-	-

infacmd isp Command	Privilege Group	Privilege Name	Permission On
AddAlertUser (for your user account)	-	-	-
AddAlertUser (for other users)	Security Administration	Manage Users, Groups, and Roles	-
AddConnectionPermissions	-	-	Grant on connection
AddDomainLink	-	-	-
AddDomainNode	Domain Administration	Manage Nodes and Grids	Domain and node
AssignGroupPermission (on application services or license objects)	Domain Administration	Manage Services	Application service or license object
AssignGroupPermission (on domain)	-	-	-
AssignGroupPermission (on folders)	Domain Administration	Manage Domain Folders	Folder
AssignGroupPermission (on nodes and grids)	Domain Administration	Manage Nodes and Grids	Node or grid
AssignGroupPermission (on operating system profiles)	-	-	-
AddGroupPrivilege	Security Administration	Grant Privileges and Roles	Domain, Metadata Manager Service, Model Repository Service, or PowerCenter Repository Service.
AddLicense	Domain Administration	Manage Services	Domain or parent folder
AddNodeResource	Domain Administration	Manage Nodes and Grids	Node
AddRolePrivilege	Security Administration	Manage Users, Groups, and Roles	-
AddServiceLevel	-	-	-
AssignUserPermission (on application services or license objects)	Domain Administration	Manage Services	Application service or license object

infacmd isp Command	Privilege Group	Privilege Name	Permission On
AssignUserPermission (on domain)	-	-	-
AssignUserPermission (on folders)	Domain Administration	Manage Domain Folders	Folder
AssignUserPermission (on nodes or grids)	Domain Administration	Manage Nodes and Grids	Node or grid
AssignUserPermission (on operating system profiles)	-	-	-
AssignUserPrivilege	Security Administration	Grant Privileges and Roles	Domain, Metadata Manager Service, Model Repository Service, or PowerCenter Repository Service.
AssignUserToGroup	Security Administration	Manage Users, Groups, and Roles	-
AssignedToLicense	Domain Administration	Manage Services	License object and application service
AssignISTOMMService	Domain Administration	Manage Services	Metadata Manager Service
AssignLicense	Domain Administration	Manage Services	License object and application service
AssignRoleToGroup	Security Administration	Grant Privileges and Roles	Domain, Metadata Manager Service, Model Repository Service, or PowerCenter Repository Service.
AssignRoleToUser	Security Administration	Grant Privileges and Roles	Domain, Metadata Manager Service, Model Repository Service, or PowerCenter Repository Service.
AssignRSToWSHubService	Domain Administration	Manage Services	PowerCenter Repository Service and Web Services Hub
ConvertLogFile	-	-	Domain or application service
CreateFolder	Domain Administration	Manage Domain Folders	Domain or parent folder
CreateConnection	-	-	-

infacmd isp Command	Privilege Group	Privilege Name	Permission On
CreateGrid	Domain Administration	Manage Nodes and Grids	Domain or parent folder and nodes assigned to grid
CreateGroup	Security Administration	Manage Users, Groups, and Roles	-
CreateIntegrationService	Domain Administration	Manage Services	Domain or parent folder, node or grid where PowerCenter Integration Service runs, license object, and associated PowerCenter Repository Service
CreateMMService	Domain Administration	Manage Services	Domain or parent folder, node where Metadata Manager Service runs, license object, and associated PowerCenter Integration Service and PowerCenter Repository Service
CreateOSProfile	-	-	-
CreateRepositoryService	Domain Administration	Manage Services	Domain or parent folder, node where PowerCenter Repository Service runs, and license object
CreateRole	Security Administration	Manage Users, Groups, and Roles	-
CreateSAPBWService	Domain Administration	Manage Services	Domain or parent folder, node or grid where SAP BW Service runs, license object, and associated PowerCenter Integration Service
CreateUser	Security Administration	Manage Users, Groups, and Roles	-

infacmd isp Command	Privilege Group	Privilege Name	Permission On
CreateWSHubService	Domain Administration	Manage Services	Domain or parent folder, node or grid where Web Services Hub runs, license object, and associated PowerCenter Repository Service
DisableNodeResource	Domain Administration	Manage Nodes and Grids	Node
DisableService (for Metadata Manager Service)	Domain Administration	Manage Service Execution	Metadata Manager Service and associated PowerCenter Integration Service and PowerCenter Repository Service
DisableService (for all other application services)	Domain Administration	Manage Service Execution	Application service
DisableServiceProcess	Domain Administration	Manage Service Execution	Application service
DisableUser	Security Administration	Manage Users, Groups, and Roles	-
EditUser	Security Administration	Manage Users, Groups, and Roles	-
EnableNodeResource	Domain Administration	Manage Nodes and Grids	Node
EnableService (for Metadata Manager Service)	Domain Administration	Manage Service Execution	Metadata Manager Service, and associated PowerCenter Integration Service and PowerCenter Repository Service
EnableService (for all other application services)	Domain Administration	Manage Service Execution	Application service
EnableServiceProcess	Domain Administration	Manage Service Execution	Application service
EnableUser	Security Administration	Manage Users, Groups, and Roles	-
ExportDomainObjects (for users, groups, and roles)	Security Administration	Manage Users, Groups, and Roles	-

infacmd isp Command	Privilege Group	Privilege Name	Permission On
ExportDomainObjects (for connections)	Domain Administration	Manage Connections	Read on connections
ExportUsersAndGroups	Security Administration	Manage Users, Groups, and Roles	-
generateHadoopConnectionFromHiveConection	-	-	-
GetFolderInfo	-	-	Folder
GetLastError	-	-	Application service
GetLog	-	-	Domain or application service
GetNodeName	-	-	Node
GetServiceOption	-	-	Application service
GetServiceProcessOption	-	-	Application service
GetServiceProcessStatus	-	-	Application service
GetServiceStatus	-	-	Application service
GetSessionLog	Run-time Objects	Monitor	Read on repository folder
GetWorkflowLog	Run-time Objects	Monitor	Read on repository folder
Help	-	-	-
ImportDomainObjects (for users, groups, and roles)	Security Administration	Manage Users, Groups, and Roles	-
ImportDomainObjects (for connections)	Domain Administration	Manage Connections	Write on connections
ImportUsersAndGroups	Security Administration	Manage Users, Groups, and Roles	-
ListAlertUsers	-	-	Domain
ListAllGroups	-	-	-
ListAllRoles	-	-	-
ListAllUsers	-	-	-
ListConnectionOptions	-	-	Read on connection
ListConnections	-	-	-

infacmd isp Command	Privilege Group	Privilege Name	Permission On
ListConnectionPermissions	-	-	-
ListConnectionPermissions by Group	-	-	-
ListConnectionPermissions by User	-	-	-
ListDomainLinks	-	-	Domain
ListDomainOptions	-	-	Domain
ListFolders	-	-	Folders
ListGridNodes	-	-	-
ListGroupsForUser	-	-	Domain
ListGroupPermissions	-	-	-
ListGroupPrivilege	Security Administration	Grant Privileges and Roles	Domain, Metadata Manager Service, Model Repository Service, or PowerCenter Repository Service.
ListLDAPConnectivity	Security Administration	Manage Users, Groups, and Roles	-
ListLicenses	-	-	License objects
listMonitoringOptions	Monitoring	Monitoring Configuration	Domain
ListNodeOptions	-	-	Node
ListNodes	-	-	-
ListNodeResources	-	-	Node
ListPlugins	-	-	-
ListRepositoryLDAPConfiguration	-	-	Domain
ListRolePrivileges	-	-	-
ListSecurityDomains	Security Administration	Manage Users, Groups, and Roles	-
ListServiceLevels	-	-	Domain
ListServiceNodes	-	-	Application service
ListServicePrivileges	-	-	-

infacmd isp Command	Privilege Group	Privilege Name	Permission On
ListServices	-	-	-
ListSMTPOptions	-	-	Domain
ListUserPermissions	-	-	-
ListUserPrivilege	Security Administration	Grant Privileges and Roles	Domain, Metadata Manager Service, Model Repository Service, or PowerCenter Repository Service.
MoveFolder	Domain Administration	Manage Domain Folders	Original and destination folders
MoveObject (for application services or license objects)	Domain Administration	Manage Services	Original and destination folders
MoveObject (for nodes or grids)	Domain Administration	Manage Nodes and Grids	Original and destination folders
Ping	-	-	-
PurgeLog	-	-	-
purgeMonitoringData	Monitoring	Monitoring Configuration	Domain
RemoveAlertUser (for your user account)	-	-	-
RemoveAlertUser (for other users)	Security Administration	Manage Users, Groups, and Roles	-
RemoveConnection	-	-	Write on connection
RemoveConnectionPermissions	-	-	Grant on connection
RemoveDomainLink	-	-	-
RemoveFolder	Domain Administration	Manage Domain Folders	Domain or parent folder and folder being removed
RemoveGrid	Domain Administration	Manage Nodes and Grids	Domain or parent folder and grid
RemoveGroup	Security Administration	Manage Users, Groups, and Roles	-

infacmd isp Command	Privilege Group	Privilege Name	Permission On
RemoveGroupPrivilege	Security Administration	Grant Privileges and Roles	Domain, Metadata Manager Service, Model Repository Service, or PowerCenter Repository Service.
RemoveLicense	Domain Administration	Manage Services	Domain or parent folder and license object
RemoveNode	Domain Administration	Manage Nodes and Grids	Domain or parent folder and node
RemoveNodeResource	Domain Administration	Manage Nodes and Grids	Node
RemoveOSProfile	-	-	-
RemoveRole	Security Administration	Manage Users, Groups, and Roles	-
RemoveRolePrivilege	Security Administration	Manage Users, Groups, and Roles	-
RemoveService	Domain Administration	Manage Services	Domain or parent folder and application service
RemoveServiceLevel	-	-	-
RemoveUser	Security Administration	Manage Users, Groups, and Roles	-
RemoveUserFromGroup	Security Administration	Manage Users, Groups, and Roles	-
RemoveUserPrivilege	Security Administration	Grant Privileges and Roles	Domain, Metadata Manager Service, Model Repository Service, or PowerCenter Repository Service.
RenameConnection	-	-	Write on connection
ResetPassword (for your user account)	-	-	-
ResetPassword (for other users)	Security Administration	Manage Users, Groups, and Roles	-
RunCPUProfile	Domain Administration	Manage Nodes and Grids	Node
SetConnectionPermission	-	-	Grant on connection

infacmd isp Command	Privilege Group	Privilege Name	Permission On
SetLDAPConnectivity	Security Administration	Manage Users, Groups, and Roles	-
SetRepositoryLDAPConfiguration	-	-	Domain
ShowLicense	-	-	License object
ShutdownNode	Domain Administration	Manage Nodes and Grids	Node
SwitchToGatewayNode	-	-	-
SwitchToWorkerNode	-	-	-
UnAssignISMMService	Domain Administration	Manage Services	PowerCenter Integration Service and Metadata Manager Service
UnassignLicense	Domain Administration	Manage Services	License object and application service
UnAssignRoleFromGroup	Security Administration	Grant Privileges and Roles	Domain, Metadata Manager Service, Model Repository Service, or PowerCenter Repository Service.
UnAssignRoleFromUser	Security Administration	Grant Privileges and Roles	Domain, Metadata Manager Service, Model Repository Service, or PowerCenter Repository Service.
UnassignRSWSHubService	Domain Administration	Manage Services	PowerCenter Repository Service and Web Services Hub
UnassociateDomainNode	Domain Administration	Manage Nodes and Grids	Node
UpdateConnection	-	-	Write on connection
UpdateDomainOptions	-	-	-
UpdateFolder	Domain Administration	Manage Domain Folders	Folder
UpdateGatewayInfo	-	-	-
UpdateGrid	Domain Administration	Manage Nodes and Grids	Grid and nodes

infacmd isp Command	Privilege Group	Privilege Name	Permission On
UpdateIntegrationService	Domain Administration	Manage Services	PowerCenter Integration Service
UpdateLicense	Domain Administration	Manage Services	License object
UpdateMMService	Domain Administration	Manage Services	Metadata Manager Service
updateMonitoringOptions	Monitoring	Monitoring Configuration	Domain
UpdateNodeOptions	Domain Administration	Manage Nodes and Grids	Node
UpdateNodeRole	Domain Administration	Manage Nodes and Grids	Node
UpdateOSProfile	Security Administration	Manage Users, Groups, and Roles	Operating system profile
UpdateRepositoryService	Domain Administration	Manage Services	PowerCenter Repository Service
UpdateSAPBWService	Domain Administration	Manage Services	SAP BW Service
UpdateServiceLevel	-	-	-
UpdateServiceProcess	Domain Administration	Manage Services	PowerCenter Integration Service Each node added to the PowerCenter Integration Service
UpdateSMTPOptions	-	-	-
UpdateWSHubService	Domain Administration	Manage Services	Web Services Hub

infacmd mrs Commands

To run *infacmd mrs* commands, users must have one of the listed sets of domain privileges, Model Repository Service privileges, and Model repository object permissions.

Users can run the following commands, which are related to locking and versioning operations, on objects they own. Running the commands on objects that other users own requires the Manage Team-based Development privilege:

- CheckInObject
- ListCheckedOutObjects

- ListLockedObjects
- UndoCheckout
- UnlockObject

The following table lists the required privileges and permissions for *infacmd mrs* commands:

infacmd mrs Command	Privilege Group	Privilege Name	Permission On...
BackupContents	Domain Administration	Manage Service	Domain or node where the Model Repository Service runs
CheckInObject	Domain Administration	Manage Team-based Development	The Model Repository Service
CreateContents	Domain Administration	Manage Service	Domain or node where the Model Repository Service runs
CreateFolder	Domain Administration	For Developer tool: - Access Developer For Analyst tool: - Access Analyst - Discovery workspace access	The Model Repository Service
CreateProject	Domain Administration	Create, Edit and Delete Projects	The Model Repository Service
CreateService	Domain Administration	Manage Service	Domain or node where the Model Repository Service runs
DeleteContents	Domain Administration	Manage Service	Domain or node where the Model Repository Service runs
DeleteFolder	Domain Administration	For Developer tool: - Access Developer For Analyst tool: - Access Analyst - Discovery workspace access	The Model Repository Service
DeleteProject	Domain Administration	Create, Edit and Delete Projects	The Model Repository Service
ListBackupFiles	Domain Administration	Manage Service	Domain or node where the Model Repository Service runs
ListCheckedOutObjects	Domain Administration	Manage Team-based Development	The Model Repository Service
ListFolders	Domain Administration	Manage Service	Domain or node where the Model Repository Service runs

infacmd mrs Command	Privilege Group	Privilege Name	Permission On...
ListLockedObjects	Domain Administration	Manage Team-based Development	The Model Repository Service
ListProjects	Domain Administration	For Developer tool: - Access Developer For Analyst tool: - Access Analyst - Discovery workspace access	Domain or node where the Model Repository Service runs
ListServiceOptions	-	-	The Model Repository Service
ListServiceProcessOptions	-	-	The Model Repository Service
PopulateVCS	Domain Administration	Manage Team-based Development	The Model Repository Service
ReassignCheckedOutObject	Domain Administration	Manage Team-based Development	The Model Repository Service
RebuildDependencyGraph	-	-	The Model Repository Service
RenameFolder	Domain Administration	For Developer tool: - Access Developer For Analyst tool: - Access Analyst - Discovery workspace access	The Model Repository Service
RestoreContents	Domain Administration	Manage Service	Domain or node where the Model Repository Service runs
UndoCheckout	Domain Administration	Manage Team-based Development	The Model Repository Service
UnlockObject	Domain Administration	Manage Team-based Development	The Model Repository Service
UpdateServiceOptions	Domain Administration	Manage Service	The Model Repository Service
UpdateServiceProcessOptions	Domain Administration	Manage Service	The Model Repository Service
UpgradeContents	Model Repository Service Administration	Manage Service	The Model Repository Service

infacmd ms Commands

To run *infacmd ms* commands, users must have one of the listed sets of domain object permissions.

The following table lists the required privileges and permissions for *infacmd ms* commands:

infacmd ms Command	Privilege Group	Privilege Name	Permission On...
GetRequestLog	-	-	-
ListMappings	-	-	-
ListMappingParams	-	-	-
RunMapping	-	-	Execute on connection objects used by the mapping

infacmd oie Commands

To run *infacmd oie* commands, users must have one of the listed Model repository object permissions.

The following table lists the required permissions for *infacmd oie* commands:

infacmd oie Command	Privilege Group	Privilege Name	Permission On...
ExportObjects	-	-	Read on project
ImportObjects	-	-	Write on project

infacmd ps Commands

To run *infacmd ps* commands, users must have one of the listed sets of profiling privileges and domain object permissions.

The following table lists the required privileges and permissions for *infacmd ps* commands:

infacmd ps Command	Privilege Group	Privilege Name	Permission On...
CreateWH	-	-	-
DropWH	-	-	-
Execute	-	-	Read on project Execute on the source connection object

infacmd ps Command	Privilege Group	Privilege Name	Permission On...
List	-	-	Read on project
Purge	-	-	Read and write on project

infacmd ps Command	Privilege Group	Privilege Name	Permission On...
CreateWH	-	-	-
DropWH	-	-	-

infacmd pwx Commands

To run *infacmd pwx* commands, users must have one of the listed sets of PowerExchange application service permissions and privileges.

The following table lists the required privileges and permissions for *infacmd pwx* commands:

infacmd pwx Command	Privilege Group	Privilege Name	Permission On...
CloseForceListener	Management Commands	closeforce	-
CloseListener	Management Commands	close	-
CondenseLogger	Management Commands	condense	-
CreateListenerService	Domain Administration	Manage Service	Domain or node where the PowerExchange application service runs
CreateLoggerService	Domain Administration	Manage Service	Domain or node where the PowerExchange application service runs
DisplayAllLogger	Informational Commands	displayall	-
DisplayCPULogger	Informational Commands	displaycpu	-
DisplayEventsLogger	Informational Commands	displayevents	-

infacmd pwx Command	Privilege Group	Privilege Name	Permission On...
DisplayMemoryLogger	Informational Commands	displaymemory	-
DisplayRecordsLogger	Informational Commands	displayrecords	-
DisplayStatusLogger	Informational Commands	displaystatus	-
FileSwitchLogger	Management Commands	fileswitch	-
ListTaskListener	Informational Commands	listtask	-
ShutDownLogger	Management Commands	shutdown	-
StopTaskListener	Management Commands	stoptask	-
UpdateListenerService	Domain Administration	Manage Service	Domain or node where the PowerExchange application service runs
UpdateLoggerService	Domain Administration	Manage Service	Domain or node where the PowerExchange application service runs

infacmd rms Commands

To run *infacmd rms* commands, users must have one of the listed sets of domain privileges and permissions

The following table lists the required privileges and permissions for *infacmd rms* commands:

infacmd rms Command	Privilege Group	Privilege Name	Permission On
ListComputeNodeAttributes	Domain Administration	-	Resource Manager Service
ListServiceOptions	Domain Administration	-	Resource Manager Service
SetComputeNodeAttributes	Domain Administration	Manage Services	Resource Manager Service
UpdateServiceOptions	Domain Administration	Manage Services	Resource Manager Service

infacmd rtm Commands

To run *infacmd rtm* commands, users must have one of the listed sets of Model Repository Service privileges and domain object permissions.

The following table lists the required privileges and permissions for *infacmd rtm* commands:

infacmd rtm Command	Privilege Group	Privilege Name	Permission On...
Deployimport	-	-	-
Export	-	-	Read on the project that contains reference tables to be exported
Import	-	-	Read and Write on the project where reference tables are imported

infacmd sch commands

To run *infacmd sch* commands, users must have one of the listed sets of privileges and permissions.

The following table lists the required privileges and permissions for *infacmd sch* commands:

infacmd sch Command	Privilege Group	Privilege Name	Permission On
CreateSchedule	Scheduler Privileges	Create Schedule	Scheduler Service
DeleteSchedule	Scheduler Privileges	Delete Schedule	Scheduler Service
ListSchedule	Scheduler Privileges	View Schedules	Scheduler Service
ListServiceOptions	Domain Privileges	Manage Services	Scheduler Service
ListServiceProcessOptions	Domain Privileges	Manage Services	Scheduler Service
PauseAll	Scheduler Privileges	Edit Schedule	Scheduler Service
PauseSchedule	Scheduler Privileges	Edit Schedule	Scheduler Service
ResumeAll	Scheduler Privileges	Edit Schedule	Scheduler Service
ResumeSchedule	Scheduler Privileges	Edit Schedule	Scheduler Service
UpdateSchedule	Scheduler Privileges	Edit Schedule	Scheduler Service
UpdateService	Domain Privileges	Manage Services	Scheduler Service
UpdateServiceProcess	Domain Privileges	Manage Services	Scheduler Service
Upgrade	Domain Privileges	Manage Services	Scheduler Service

infacmd sql Commands

To run *infacmd sql* commands, users must have one of the listed sets of domain privileges, Data Integration Service privileges, and domain object permissions.

The following table lists the required privileges and permissions for *infacmd sql* commands:

infacmd sql Command	Privilege Group	Privilege Name	Permission On...
ExecuteSQL	-	-	Based on objects that you want to access in your SQL statement
ListColumnPermissions	-	-	-
ListSQLDataServiceOptions	-	-	-
ListSQLDataServicePermissions	-	-	-
ListSQLDataServices	-	-	-
ListStoredProcedurePermissions	-	-	-
ListTableOptions	-	-	-
ListTablePermissions	-	-	-
PurgeTableCache	-	-	-
RefreshTableCache	-	-	-
RenameSQLDataService	Application Administration	Manage Applications	-
SetColumnPermissions	-	-	Grant on the object
SetSQLDataServicePermissions	-	-	Grant on the object
SetStoredProcedurePermissions	-	-	Grant on the object
SetTablePermissions	-	-	Grant on the object
StartSQLDataService	Application Administration	Manage Applications	-
StopSQLDataService	Application Administration	Manage Applications	-
UpdateColumnOptions	Application Administration	Manage Applications	-
UpdateSQLDataServiceOptions	Application Administration	Manage Applications	-
UpdateTableOptions	Application Administration	Manage Applications	-

infacmd wfs Commands

To run *infacmd wfs* commands, users do not require any privileges or permissions.

pmcmd Commands

To run *pmcmd* commands, users must have the listed sets of PowerCenter Repository Service privileges and PowerCenter repository object permissions.

When the PowerCenter Integration Service runs in safe mode, users must have the Administrator role for the associated PowerCenter Repository Service to run the following commands:

- aborttask
- abortworkflow
- getrunningessionsdetails
- getservicedetails
- getsessionstatistics
- gettaskdetails
- getworkflowdetails
- recoverworkflow
- scheduleworkflow
- starttask
- startworkflow
- stoptask
- stopworkflow
- unscheduleworkflow

The following table lists the required privileges and permissions for *pmcmd* commands:

pmcmd Command	Privilege Group	Privilege Name	Permission
aborttask (started by own user account)	-	-	Read and Execute on folder
aborttask (started by other users)	Run-time Objects	Manage Execution	Read and Execute on folder
abortworkflow (started by own user account)	-	-	Read and Execute on folder
abortworkflow (started by other users)	Run-time Objects	Manage Execution	Read and Execute on folder
connect	-	-	-
disconnect	-	-	-

pmcmd Command	Privilege Group	Privilege Name	Permission
exit	-	-	-
getrunningsessionsdetails	Run-time Objects	Monitor	-
getservicedetails	Run-time Objects	Monitor	Read on folder
getserviceproperties	-	-	-
getsessionstatistics	Run-time Objects	Monitor	Read on folder
gettaskdetails	Run-time Objects	Monitor	Read on folder
getworkflowdetails	Run-time Objects	Monitor	Read on folder
help	-	-	-
pingservice	-	-	-
recoverworkflow (started by own user account)	Run-time Objects	Execute	Read and Execute on folder Read and Execute on connection object Permission on operating system profile (if applicable)
recoverworkflow (started by other users)	Run-time Objects	Manage Execution	Read and Execute on folder Read and Execute on connection object Permission on operating system profile (if applicable)
scheduleworkflow	Run-time Objects	Manage Execution	Read and Execute on folder Read and Execute on connection object Permission on operating system profile (if applicable)
setfolder	-	-	Read on folder
setnowait	-	-	-
setwait	-	-	-
showsettings	-	-	-
starttask	Run-time Objects	Execute	Read and Execute on folder Read and Execute on connection object Permission on operating system profile (if applicable)

pmcmd Command	Privilege Group	Privilege Name	Permission
startworkflow	Run-time Objects	Execute	Read and Execute on folder Read and Execute on connection object Permission on operating system profile (if applicable)
stoptask (started by own user account)	-	-	Read and Execute on folder
stoptask (started by other users)	Run-time Objects	Manage Execution	Read and Execute on folder
stopworkflow (started by own user account)	-	-	Read and Execute on folder
stopworkflow (started by other users)	Run-time Objects	Manage Execution	Read and Execute on folder
unscheduleworkflow	Run-time Objects	Manage Execution	Read and Execute on folder
unsetfolder	-	-	Read on folder
version	-	-	-
waittask	Run-time Objects	Monitor	Read on folder
waitworkflow	Run-time Objects	Monitor	Read on folder

pmrep Commands

Users must have the Access Repository Manager privilege to run all *pmrep* commands except for the following commands:

- Run
- Create
- Restore
- Upgrade
- Version
- Help

To run *pmrep* commands, users must have one of the listed sets of domain privileges, PowerCenter Repository Service privileges, domain object permissions, and PowerCenter repository object permissions.

Users must be the object owner or have the Administrator role for the PowerCenter Repository Service to run the following commands:

- AssignPermission
- ChangeOwner

- DeleteConnection
- DeleteDeploymentGroup
- DeleteFolder
- DeleteLabel
- ModifyFolder (to change owner, configure permissions, designate the folder as shared, or edit the folder name or description)

The following table lists the required privileges and permissions for *pmrep* commands:

pmrep Command	Privilege Group	Privilege Name	Permission
AddToDeploymentGroup	Global Objects	Manage Deployment Groups	Read on original folder Read and Write on deployment group
ApplyLabel	-	-	Read on folder Read and Execute on label
AssignPermission	-	-	-
BackUp	Domain Administration	Manage Services	Permission on PowerCenter Repository Service
ChangeOwner	-	-	-
CheckIn (for your own checkouts)	Design Objects	Create, Edit, and Delete	Read and Write on folder
CheckIn (for your own checkouts)	Sources and Targets	Create, Edit, and Delete	Read and Write on folder
CheckIn (for your own checkouts)	Run-time Objects	Create, Edit, and Delete	Read and Write on folder
CheckIn (for others' checkouts)	Design Objects	Manage Versions	Read and Write on folder
CheckIn (for others' checkouts)	Sources and Targets	Manage Versions	Read and Write on folder
CheckIn (for others' checkouts)	Run-time Objects	Manage Versions	Read and Write on folder
CleanUp	-	-	-
ClearDeploymentGroup	Global Objects	Manage Deployment Groups	Read and Write on deployment group
Connect	-	-	-
Create	Domain Administration	Manage Services	Permission on PowerCenter Repository Service
CreateConnection	Global Objects	Create Connections	-

pmrep Command	Privilege Group	Privilege Name	Permission
CreateDeploymentGroup	Global Objects	Manage Deployment Groups	-
CreateFolder	Folders	Create	-
CreateLabel	Global Objects	Create Labels	-
Delete	Domain Administration	Manage Services	Permission on PowerCenter Repository Service
DeleteConnection	-	-	-
DeleteDeploymentGroup	-	-	-
DeleteFolder	-	-	-
DeleteLabel	-	-	-
DeleteObject	Design Objects	Create, Edit, and Delete	Read and Write on folder
DeleteObject	Sources and Targets	Create, Edit, and Delete	Read and Write on folder
DeleteObject	Run-time Objects	Create, Edit, and Delete	Read and Write on folder
DeployDeploymentGroup	Global Objects	Manage Deployment Groups	Read on original folder Read and Write on destination folder Read and Execute on deployment group
DeployFolder	Folders	Copy on original repository Create on destination repository	Read on folder
ExecuteQuery	-	-	Read and Execute on query
Exit	-	-	-
FindCheckout	-	-	Read on folder
GetConnectionDetails	-	-	Read on connection object
Help	-	-	-
KillUserConnection	Domain Administration	Manage Services	Permission on PowerCenter Repository Service
ListConnections	-	-	Read on connection object
ListObjectDependencies	-	-	Read on folder

pmrep Command	Privilege Group	Privilege Name	Permission
ListObjects	-	-	Read on folder
ListTablesBySess	-	-	Read on folder
ListUserConnections	Domain Administration	Manage Services	Permission on PowerCenter Repository Service
ModifyFolder (to change owner, configure permissions, designate the folder as shared, or edit the folder name or description)	-	-	-
ModifyFolder (to change status)	Folders	Manage Versions	Read and Write on folder
Notify	Domain Administration	Manage Services	Permission on PowerCenter Repository Service
ObjectExport	-	-	Read on folder
ObjectImport	Design Objects	Create, Edit, and Delete	Read and Write on folder
ObjectImport	Sources and Targets	Create, Edit, and Delete	Read and Write on folder
ObjectImport	Run-time Objects	Create, Edit, and Delete	Read and Write on folder
PurgeVersion	Design Objects	Manage Versions	Read and Write on folder Read, Write, and Execute on query if you specify a query name
PurgeVersion	Sources and Targets	Manage Versions	Read and Write on folder Read, Write, and Execute on query if you specify a query name
PurgeVersion	Run-time Objects	Manage Versions	Read and Write on folder Read, Write, and Execute on query if you specify a query name
PurgeVersion (to purge objects at the folder level)	Folders	Manage Versions	Read and Write on folder
PurgeVersion (to purge objects at the repository level)	Domain Administration	Manage Services	Permission on PowerCenter Repository Service
Register	Domain Administration	Manage Services	Permission on PowerCenter Repository Service
RegisterPlugin	Domain Administration	Manage Services	Permission on PowerCenter Repository Service

pmrep Command	Privilege Group	Privilege Name	Permission
Restore	Domain Administration	Manage Services	Permission on PowerCenter Repository Service
RollbackDeployment	Global Objects	Manage Deployment Groups	Read and Write on destination folder
Run	-	-	-
ShowConnectionInfo	-	-	-
SwitchConnection	Run-time Objects	Create, Edit, and Delete	Read and Write on folder Read on connection object
TruncateLog	Run-time Objects	Manage Execution	Read and Execute on folder
UndoCheckout (for your own checkouts)	Design Objects	Create, Edit, and Delete	Read and Write on folder
UndoCheckout (for your own checkouts)	Sources and Targets	Create, Edit, and Delete	Read and Write on folder
UndoCheckout (for your own checkouts)	Run-time Objects	Create, Edit, and Delete	Read and Write on folder
UndoCheckout (for others' checkouts)	Design Objects	Manage Versions	Read and Write on folder
UndoCheckout (for others' checkouts)	Sources and Targets	Manage Versions	Read and Write on folder
UndoCheckout (for others' checkouts)	Run-time Objects	Manage Versions	Read and Write on folder
Unregister	Domain Administration	Manage Services	Permission on PowerCenter Repository Service
UnregisterPlugin	Domain Administration	Manage Services	Permission on PowerCenter Repository Service
UpdateConnection	-	-	Read and Write on connection object
UpdateEmailAddr	Run-time Objects	Create, Edit, and Delete	Read and Write on folder
UpdateSeqGenVals	Design Objects	Create, Edit, and Delete	Read and Write on folder
UpdateSrcPrefix	Run-time Objects	Create, Edit, and Delete	Read and Write on folder
UpdateStatistics	Domain Administration	Manage Services	Permission on PowerCenter Repository Service

pmrep Command	Privilege Group	Privilege Name	Permission
UpdateTargPrefix	Run-time Objects	Create, Edit, and Delete	Read and Write on folder
Upgrade	Domain Administration	Manage Services	Permission on PowerCenter Repository Service
Validate	Design Objects	Create, Edit, and Delete	Read and Write on folder
Validate	Run-time Objects	Create, Edit, and Delete	Read and Write on folder
Version	-	-	-

APPENDIX B

Custom Roles

This appendix includes the following topics:

- [Analyst Service Custom Role, 238](#)
- [Metadata Manager Service Custom Roles, 239](#)
- [Operator Custom Role, 240](#)
- [PowerCenter Repository Service Custom Roles, 241](#)
- [Test Data Manager Custom Roles, 242](#)

Analyst Service Custom Role

The Analyst Service Business Glossary Consumer is a custom Analyst Service role.

The following table lists the default privilege assigned to the Analyst Service Business Glossary Consumer custom role:

Privilege Group	Privilege Name
Workspace Access	Glossary Workspace

Metadata Manager Service Custom Roles

Metadata Manager Service custom roles include the Metadata Manager Advanced User, Metadata Manager Basic User, and Metadata Manager Intermediate User roles.

Metadata Manager Advanced User

The following table lists the default privileges assigned to the Metadata Manager Advanced User custom role:

Privilege Group	Privilege Name
Catalog	<ul style="list-style-type: none">- Share Shortcuts- View Lineage- View Related Catalogs- View Reports- View Profile Results- View Catalog- View Relationships- Manage Relationships- View Comments- Post Comments- Delete Comments- View Links- Manage Links- View Glossary- Manage Objects
Load	<ul style="list-style-type: none">- View Resource- Load Resource- Manage Schedules- Purge Metadata- Manage Resource
Model	<ul style="list-style-type: none">- View Model- Manage Model- Export/Import Models
Security	Manage Catalog Permissions

Metadata Manager Basic User

The following table lists the default privileges assigned to the Metadata Manager Basic User custom role:

Privilege Group	Privilege Name
Catalog	<ul style="list-style-type: none">- View Lineage- View Related Catalogs- View Catalog- View Relationships- View Comments- View Links
Model	View Model

Metadata Manager Intermediate User

The following table lists the default privileges assigned to the Metadata Manager Intermediate User custom role:

Privilege Group	Privilege Name
Catalog	<ul style="list-style-type: none">- View Lineage- View Related Catalogs- View Reports- View Profile Results- View Catalog- View Relationships- View Comments- Post Comments- Delete Comments- View Links- Manage Links- View Glossary
Load	<ul style="list-style-type: none">- View Resource- Load Resource
Model	View Model

Operator Custom Role

The Operator custom role includes privileges for managing, scheduling, and monitoring application services.

The following table lists the default privileges assigned to the Operator custom role:

Privilege Group	Privilege Name
Application Administration	Manage Applications
Domain Administration	Manage Service Execution
Model Repository Service Administration	Manage Team-based Development
Monitoring	<p>The Monitoring privilege group includes the following privileges:</p> <ul style="list-style-type: none">- View: View Jobs of Other Users- View: View Statistics- View: View Reports- Access Monitoring: Access from Analyst Tool- Access Monitoring: Access from Developer Tool- Access Monitoring: Access from Administrator Tool- Perform Actions on Jobs <p>Note: In a domain that uses Kerberos authentication, users must also have the Administrator role for the Model Repository Service that is configured for monitoring.</p>

Privilege Group	Privilege Name
Scheduler	The Scheduler privilege group includes the following privileges: <ul style="list-style-type: none"> - Manage Scheduled Jobs: Create Schedule - Manage Scheduled Jobs: Delete Schedule - Manage Scheduled Jobs: Edit Schedule - Manage Scheduled Jobs: View Schedules
Tools	Access Informatica Administrator

PowerCenter Repository Service Custom Roles

The PowerCenter Repository Service custom roles include the PowerCenter Connection Administrator, PowerCenter Developer, PowerCenter Operator, and PowerCenter Repository Folder Administrator.

PowerCenter Connection Administrator

The following table lists the default privileges assigned to the PowerCenter Connection Administrator custom role:

Privilege Group	Privilege Name
Tools	Access Workflow Manager
Global Objects	Create Connections

PowerCenter Developer

The following table lists the default privileges assigned to the PowerCenter Developer custom role:

Privilege Group	Privilege Name
Tools	<ul style="list-style-type: none"> - Access Designer - Access Workflow Manager - Access Workflow Monitor
Design Objects	<ul style="list-style-type: none"> - Create, Edit, and Delete - Manage Versions
Sources and Targets	<ul style="list-style-type: none"> - Create, Edit, and Delete - Manage Versions
Run-time Objects	<ul style="list-style-type: none"> - Create, Edit, and Delete - Execute - Manage Versions - Monitor

PowerCenter Operator

The following table lists the default privileges assigned to the PowerCenter Operator custom role:

Privilege Group	Privilege Name
Tools	Access Workflow Monitor
Run-time Objects	<ul style="list-style-type: none">- Execute- Manage Execution- Monitor

PowerCenter Repository Folder Administrator

The following table lists the default privileges assigned to the PowerCenter Repository Folder Administrator custom role:

Privilege Group	Privilege Name
Tools	Access Repository Manager
Folders	<ul style="list-style-type: none">- Copy- Create- Manage Versions
Global Objects	<ul style="list-style-type: none">- Manage Deployment Groups- Execute Deployment Groups- Create Labels- Create Queries

Test Data Manager Custom Roles

The Test Data Manager custom roles include the Test Data Administrator, Test Data Developer, Test Data Project DBA, Test Data Project Developer, Test Data Project Owner, Test Data Risk Manager, Test Data Specialist, and Test Engineer.

Test Data Administrator

The following table lists the default privileges assigned to the Test Data Administrator custom role:

Privilege Group	Privilege Name
Projects	Audit Project
Administration	<ul style="list-style-type: none">- View Connections- Manage Connections- Manage Preferences

Test Data Developer

The following table lists the default privileges assigned to the Test Data Developer custom role:

Privilege Group	Privilege Name
Policies	<ul style="list-style-type: none">- View Policies- Manage Policies
Data Domains	<ul style="list-style-type: none">- View Data Domains- Manage Data Domains
Rules	<ul style="list-style-type: none">- View Masking Rules- Manage Masking Rules- View Generation Rules- Manage Generation Rules
Projects	Audit Project

Test Data Project DBA

The following table lists the default privileges assigned to the Test Data Project DBA custom role:

Privilege Group	Privilege Name
Projects	<ul style="list-style-type: none">- View Project- Execute Project- Monitor Project- Audit Project
Administration	<ul style="list-style-type: none">- View Connections- Manage Connections
Data Sets	<ul style="list-style-type: none">- View Data Set- View Data in Data Set.

Test Data Project Developer

The following table lists the default privileges assigned to the Test Data Project Developer custom role:

Privilege Group	Privilege Name
Policies	View Policies
Rules	<ul style="list-style-type: none">- View Masking Rules- View Generation Rules- Manage Generation Rules
Data Domains	View Data Domains
Projects	<ul style="list-style-type: none">- View Project- Discover Project- Execute Project- Monitor Project- Audit Project- Import Metadata

Privilege Group	Privilege Name
Data Masking	<ul style="list-style-type: none"> - View Data Masking - Manage Data Masking
Data Subset	<ul style="list-style-type: none"> - View Data Subset - Manage Data Subset
Data Generation	<ul style="list-style-type: none"> - View Data Generation - Manage Data Generation
Administration	<ul style="list-style-type: none"> - View Connections - Manage Connections
Data Sets	<ul style="list-style-type: none"> - View Data Set - View Data in Data Set

Test Data Project Owner

The following table lists the default privileges assigned to the Test Data Project Owner custom role:

Privilege Group	Privilege Name
Policies	View Policies
Rules	<ul style="list-style-type: none"> - View Masking Rules - View Generation Rules - Manage Generation Rules
Data Domains	View Data Domains
Projects	<ul style="list-style-type: none"> - View Project - Manage Project - Discover Project - Execute Project - Monitor Project - Audit Project - Import Metadata
Data Masking	<ul style="list-style-type: none"> - View Data Masking - Manage Data Masking
Data Subset	<ul style="list-style-type: none"> - View Data Subset - Manage Data Subset
Data Generation	<ul style="list-style-type: none"> - View Data Generation - Manage Data Generation

Privilege Group	Privilege Name
Administration	<ul style="list-style-type: none"> - View Connections - Manage Connections
Data Sets	<ul style="list-style-type: none"> - View Data Set - View Data in Data Set - Manage Data Set - Manage Data in Data Set - Reset Data Set

Test Data Risk Manager

The following table lists the default privileges assigned to the Test Data Risk Manager custom role:

Privilege Group	Privilege Name
Policies	View Policies
Rules	<ul style="list-style-type: none"> - View Masking Rules - View Generation Rules
Data Domains	View Data Domains
Projects	Audit Project

Test Data Specialist

The following table lists the default privileges assigned to the Test Data Specialist custom role:

Privilege Group	Privilege Name
Policies	View Policies
Rules	<ul style="list-style-type: none"> - View Masking Rules - Manage Masking Rules - View Generation Rules - Manage Generation Rules
Data Domains	<ul style="list-style-type: none"> - View Data Domains - Manage Data Domains
Projects	<ul style="list-style-type: none"> - View Project - Manage Project - Discover Project - Execute Project - Monitor Project - Audit Project - Import Metadata
Data Masking	<ul style="list-style-type: none"> - View Data Masking - Manage Data Masking
Data Subset	<ul style="list-style-type: none"> - View Data Subset - Manage Data Subset

Privilege Group	Privilege Name
Data Generation	<ul style="list-style-type: none"> - View Data Generation - Manage Data Generation
Administration	<ul style="list-style-type: none"> - View Connections - Manage Connections
Data Sets	<ul style="list-style-type: none"> - View Data Set - View Data in Data Set - Manage Data Set - Manage Data in Data Set - Reset Data Set

Test Engineer

The following table lists the default privileges assigned to the Test Engineer custom role:

Privilege Group	Privilege Name
Projects	<ul style="list-style-type: none"> - View Project - Monitor Project
Data Sets	<ul style="list-style-type: none"> - View Data Set - Manage Data Set - Reset Data Set - View Data in Data Set - Manage Data in Data Set

APPENDIX C

Default List of Cipher Suites

By default, the Informatica domain uses the following cipher suites for secure communication within the domain and secure client connections:

- TLS_ECDHE_ECDSA_WITH_AES_256_CBC_SHA
- TLS_ECDHE_RSA_WITH_AES_256_CBC_SHA
- TLS_RSA_WITH_AES_256_CBC_SHA
- TLS_ECDH_ECDSA_WITH_AES_256_CBC_SHA
- TLS_ECDH_RSA_WITH_AES_256_CBC_SHA
- TLS_DHE_RSA_WITH_AES_256_CBC_SHA
- TLS_DHE_DSS_WITH_AES_256_CBC_SHA
- TLS_ECDHE_ECDSA_WITH_AES_128_CBC_SHA
- TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA
- TLS_RSA_WITH_AES_128_CBC_SHA
- TLS_ECDH_ECDSA_WITH_AES_128_CBC_SHA
- TLS_ECDH_RSA_WITH_AES_128_CBC_SHA
- TLS_DHE_RSA_WITH_AES_128_CBC_SHA
- TLS_DHE_DSS_WITH_AES_128_CBC_SHA
- TLS_ECDHE_ECDSA_WITH_3DES_EDE_CBC_SHA
- TLS_ECDHE_RSA_WITH_3DES_EDE_CBC_SHA
- TLS_RSA_WITH_3DES_EDE_CBC_SHA
- TLS_ECDH_ECDSA_WITH_3DES_EDE_CBC_SHA
- TLS_ECDH_RSA_WITH_3DES_EDE_CBC_SHA
- TLS_DHE_RSA_WITH_3DES_EDE_CBC_SHA
- TLS_DHE_DSS_WITH_3DES_EDE_CBC_SHA
- TLS_ECDHE_ECDSA_WITH_AES_256_CBC_SHA384
- TLS_ECDHE_RSA_WITH_AES_256_CBC_SHA384
- TLS_RSA_WITH_AES_256_CBC_SHA256
- TLS_ECDH_ECDSA_WITH_AES_256_CBC_SHA384
- TLS_ECDH_RSA_WITH_AES_256_CBC_SHA384
- TLS_DHE_RSA_WITH_AES_256_CBC_SHA256
- TLS_DHE_DSS_WITH_AES_256_CBC_SHA256
- TLS_ECDHE_ECDSA_WITH_AES_128_CBC_SHA256

- TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA256
- TLS_RSA_WITH_AES_128_CBC_SHA256
- TLS_ECDH_ECDSA_WITH_AES_128_CBC_SHA256
- TLS_ECDH_RSA_WITH_AES_128_CBC_SHA256
- TLS_DHE_RSA_WITH_AES_128_CBC_SHA256
- TLS_DHE_DSS_WITH_AES_128_CBC_SHA256

INDEX

A

- accounts
 - changing the password [109](#)
- Active Directory Federation Services
 - configuring for single sign-on [91](#)
- Administrator
 - role [177](#)
- administrators
 - application client [115](#)
 - default [114](#)
 - domain [115](#)
- Analyst Service
 - custom roles [238](#)
 - privileges [146](#)
- application
 - permissions [194](#)
- application services
 - authorization [106](#)
 - permissions [186](#)
 - user synchronization [106](#)
- as
 - permissions by command [209](#)
 - privileges by command [209](#)
- audit reports
 - description [203](#)
 - for groups [207](#)
 - for users [207](#), [208](#)
- authentication
 - Kerberos [20](#)
 - LDAP [19](#), [22](#), [105](#)
 - native [19](#), [105](#)
 - Service Manager [105](#)
- authorization
 - application services [106](#)
 - Data Integration Service [106](#)
 - Metadata Manager Service [106](#)
 - Model Repository Service [106](#)
 - PowerCenter Repository Service [106](#)
 - Service Manager [106](#)

B

- Browse privilege group
 - description [148](#)

C

- cacerts truststore file [26](#)
- changing
 - password for user account [109](#)
- cipher suites
 - advanced [72](#)
 - configuring [71](#)

- cipher suites (*continued*)
 - Java Cryptography Extension (JCE) [72](#)
- client configuration
 - secure domain [63](#)
- Cloud Administration privilege group
 - domain [145](#)
- column level security
 - restricting columns [199](#)
- command line programs
 - privileges [209](#)
- connection objects
 - privileges for PowerCenter [164](#)
- connections
 - default permissions [192](#)
 - permission types [192](#)
 - permissions [191](#)
- Content Management Service
 - privileges [147](#)
- convertUserActivityLog
 - user activity logs [121](#)
- Create Reference Tables
 - privilege [147](#)
- custom roles
 - Analyst Service [238](#)
 - assigning to users and groups [180](#)
 - creating [179](#)
 - deleting [180](#)
 - description [176](#), [179](#)
 - editing [179](#)
 - Metadata Manager Service [239](#)
 - Operator [240](#)
 - PowerCenter Repository Service [241](#)
 - privileges, assigning [180](#)

D

- Data Integration Service
 - authorization [106](#)
 - privileges [147](#)
- default administrator
 - description [114](#)
 - modifying [114](#)
 - passwords, changing [114](#)
- deployment groups
 - privileges for PowerCenter [164](#)
- design objects
 - description [155](#)
 - privileges [155](#)
- Design Objects privilege group
 - description [155](#)
- direct permission
 - description [185](#)
- dis
 - permissions by command [210](#)
 - privileges by command [210](#)

- domain
 - administration privileges [139](#)
 - administrator [115](#)
 - Administrator role [177](#)
 - privileges [137](#)
 - security administration privileges [138](#)
 - user security [110](#)
 - user synchronization [106](#)
 - users with privileges [182](#)
- Domain Administration privilege group
 - description [139](#)
- domain administrator
 - description [115](#)
- domain objects
 - permissions [186](#)
- domain permissions
 - direct [185](#)
 - effective [185](#)
 - inherited [185](#)

E

- Edit Reference Table Metadata
 - privilege [147](#)
- effective permission
 - description [185](#)
- environment variables
 - INFA_TRUSTSTORE [63](#)
 - INFA_TRUSTSTORE_PASSWORD [63](#)
- es
 - permissions by command [211](#)
 - privileges by command [211](#)
- Everyone group
 - description [113](#)

F

- filters
 - getUserActivityLog [121](#)
- folders
 - permissions [186](#)
 - privileges [154](#)
- Folders privilege group
 - description [154](#)

G

- getUserActivityLog
 - filters [121](#)
 - user activity logs [121](#)
- global objects
 - privileges for PowerCenter [164](#)
- Global Objects privilege group
 - description [164](#)
- grids
 - permissions [186](#)
- group description
 - invalid characters [124](#)
- groups
 - default Everyone [113](#)
 - invalid characters [124](#)
 - managing [124](#)
 - overview [108](#)
 - parent group [124](#)
 - privileges, assigning [180](#)

- groups (*continued*)
 - roles, assigning [180](#)
 - synchronization [106](#)
 - valid name [124](#)

I

- IBM Tivoli Directory Server
 - LDAP authentication [22](#)
- Informatica Administrator
 - Navigator [107](#)
 - overview [103](#)
 - searching [107](#)
 - Security page [107](#)
 - tabs, viewing [103](#)
- Informatica Analyst
 - administrator [115](#)
- Informatica Developer
 - administrator [115](#)
- Informatica domain
 - permissions [110](#)
 - privileges [110](#)
 - user security [110](#)
 - users, managing [116](#)
- inherited permission
 - description [185](#)
- inherited privileges
 - description [181](#)
- ipc
 - permissions by command [211](#)
 - privileges by command [211](#)
- isp
 - permissions by command [212](#)
 - privileges by command [212](#)

K

- Kerberos authentication
 - description [20](#)
 - keytab [35](#)
 - LDAP synchronization [51](#)
 - node level [31](#)
 - overview [28](#), [29](#)
 - process level [31](#)
 - service principal accounts [34](#)
 - service principal name [35](#)
 - SPN keytab format file [39](#)
- keytool utility [26](#)

L

- labels
 - privileges for PowerCenter [164](#)
- LDAP authentication
 - description [19](#), [105](#)
 - directory services [22](#)
 - nested groups [26](#)
 - self-signed SSL certificate [26](#)
 - setting up [22](#)
 - synchronization times [25](#)
- LDAP directory service
 - connecting to [22](#)
 - nested groups [26](#)
- LDAP groups
 - importing [22](#)

LDAP groups (*continued*)

- managing [124](#)
- LDAP security domain
 - description [19](#), [20](#)
- LDAP security domains
 - configuring [23](#)
 - deleting [27](#)
 - description [21](#)
- LDAP users
 - assigning to groups [118](#)
 - enabling [118](#)
 - importing [22](#)
 - managing [116](#)
- licenses
 - permissions [186](#)
- Load privilege group
 - description [150](#)

M

- mapping
 - inherited permissions [194](#)
 - permissions [194](#)
- Metadata Manager
 - administrator [115](#)
- Metadata Manager Service
 - authorization [106](#)
 - custom roles [239](#)
 - privileges [148](#)
 - user synchronization [106](#)
 - users with privileges [182](#)
- Metadata Manager Service privileges
 - Browse privilege group [148](#)
 - Load privilege group [150](#)
 - Model privilege group [150](#)
 - Security privilege group [151](#)
- Microsoft Active Directory
 - LDAP authentication [22](#)
- Model privilege group
 - description [150](#)
- Model Repository Service
 - authorization [106](#)
 - privileges [151](#)
 - user synchronization [106](#)
 - users with privileges [182](#)
- Monitoring privilege group
 - domain [144](#)
- mrs
 - permissions by command [222](#)
 - privileges by command [222](#)
- ms
 - permissions by command [225](#)
 - privileges by command [225](#)

N

- native authentication
 - description [19](#), [105](#)
- native groups
 - adding [124](#)
 - deleting [125](#)
 - editing [125](#)
 - managing [124](#)
 - moving to another group [125](#)
 - users, assigning [118](#)

native security domain

- description [19](#)
- native users
 - adding [117](#)
 - assigning to groups [118](#)
 - deleting [119](#)
 - editing [117](#)
 - enabling [118](#)
 - managing [116](#)
 - passwords [117](#)
- Navigator
 - Security page [107](#)
- nested groups
 - LDAP authentication [26](#)
 - LDAP directory service [26](#)
- nodes
 - permissions [186](#)
- Novell eDirectory
 - LDAP authentication [22](#)

O

- object queries
 - privileges for PowerCenter [164](#)
- oie
 - permissions by command [225](#)
 - privileges by command [225](#)
- OpenLDAP
 - LDAP authentication [22](#)
- operating system profile
 - creating [129](#)
 - default [131](#)
 - deleting [131](#)
 - editing [126](#)
 - managing [126](#)
 - properties, Data Integration Service [126](#), [128](#)
 - properties, PowerCenter Integration Service [126](#)
- operating system profiles
 - permissions [186](#), [190](#)
- Operator}
 - custom roles [240](#)

P

- parent groups
 - description [124](#)
- password
 - changing for a user account [109](#)
- passwords
 - changing for default administrator [114](#)
 - native users [117](#)
 - requirements [117](#)
- permissions
 - application [194](#)
 - application services [186](#)
 - as commands [209](#)
 - connections [191](#)
 - description [184](#)
 - direct [185](#)
 - dis commands [210](#)
 - domain objects [186](#)
 - effective [185](#)
 - es commands [211](#)
 - folders [186](#)
 - grids [186](#)
 - inherited [185](#)

permissions (*continued*)

- ipc commands [211](#)
- isp commands [212](#)
- licenses [186](#)
- mapping [194](#)
- mrs commands [222](#)
- ms commands [225](#)
- nodes [186](#)
- oie commands [225](#)
- operating system profiles [186](#), [190](#)
- pmcmd commands [230](#)
- pmrep commands [232](#)
- ps commands [225](#)
- pxw commands [226](#)
- rms commands [227](#)
- rtm commands [228](#)
- sch commands [228](#)
- search filters [186](#)
- sql commands [229](#)
- SQL data service [196](#)
- types [185](#)
- virtual schema [196](#)
- virtual stored procedure [196](#)
- virtual table [196](#)
- web service [200](#)
- web service operation [200](#)
- wfs commands [230](#)
- workflow [194](#)
- working with privileges [184](#)

pmcmd

- permissions by command [230](#)
- privileges by command [230](#)

pmrep

- permissions by command [232](#)
- privileges by command [232](#)

PowerCenter Client

- administrator [115](#)

PowerCenter Repository Service

- Administrator role [177](#)
- authorization [106](#)
- custom roles [241](#)
- privileges [153](#)
- user synchronization [106](#)
- users with privileges [182](#)

PowerCenter security

- managing [107](#)

PowerExchange Listener Service

- privileges [166](#)

PowerExchange Logger Service

- privileges [167](#)

privilege groups

- Browse [148](#)
- description [136](#)
- Design Objects [155](#)
- Domain Administration [139](#)
- Folders [154](#)
- Global Objects [164](#)
- Informatica Cloud Administration [145](#)
- Load [150](#)
- Model [150](#)
- Monitoring [144](#)
- Run-time Objects [160](#)
- Security [151](#)
- Security Administration [138](#)
- Sources and Targets [158](#)
- Tools [145](#), [153](#)

privileges

- Analyst Service [146](#)

privileges (*continued*)

- as commands [209](#)
- assigning [180](#)
- command line programs [209](#)
- Content Management Service [147](#)
- Data Integration Service [147](#)
- description [135](#)
- design objects [155](#)
- dis commands [210](#)
- domain [137](#)
- domain administration [139](#)
- domain tools [145](#)
- es commands [211](#)
- folders [154](#)
- Informatica Cloud Administration [145](#)
- inherited [181](#)
- ipc commands [211](#)
- isp commands [212](#)
- Metadata Manager Service [148](#)
- Model Repository Service [151](#)
- monitoring [144](#)
- mrs commands [222](#)
- ms commands [225](#)
- oie commands [225](#)
- pmcmd commands [230](#)
- pmrep commands [232](#)
- PowerCenter global objects [164](#)
- PowerCenter Repository Service [153](#)
- PowerCenter Repository Service tools [153](#)
- PowerExchange Listener Service [166](#)
- PowerExchange Logger Service [167](#)
- ps commands [225](#)
- pxw commands [226](#)
- rms commands [227](#)
- rtm commands [228](#)
- run-time objects [160](#)
- sch commands [228](#)
- Scheduler Service [168](#)
- security administration [138](#)
- sources [158](#)
- sql commands [229](#)
- targets [158](#)
- troubleshooting [182](#)
- wfs commands [230](#)
- working with permissions [184](#)

ps

- permissions by command [225](#)
- privileges by command [225](#)

pxw

- permissions by command [226](#)
- privileges by command [226](#)

R

rms

- permissions by command [227](#)
- privileges by command [227](#)

roles

- Administrator [177](#)
- assigning [180](#)
- custom [179](#)
- description [137](#)
- managing [176](#)
- overview [109](#)
- troubleshooting [182](#)

rtm

- permissions by command [228](#)

rtm (*continued*)
 privileges by command [228](#)
run-time objects
 description [160](#)
 privileges [160](#)
Run-time Objects privilege group
 description [160](#)

S

sch
 permissions by command [228](#)
 privileges by command [228](#)
Scheduler Service
 privileges [168](#)
search filters
 permissions [186](#)
Search section
 Informatica Administrator [107](#)
secure domain
 client configuration [63](#)
security
 passwords [117](#)
 permissions [110](#)
 privileges [110](#), [135](#), [138](#)
 roles [137](#)
Security Administration privilege group
 description [138](#)
Security Assertion Markup Language (SAML)
 support for [82](#)
security domains
 configuring LDAP [23](#)
 deleting LDAP [27](#)
 LDAP [19–21](#)
 native [19](#)
Security page
 Informatica Administrator [107](#)
 Navigator [107](#)
Security privilege group
 description [151](#)
Service Manager
 authentication [105](#)
 authorization [106](#)
 single sign-on [105](#)
single sign-on
 configuring [83](#)
 description [105](#)
 overview [82](#)
sources
 privileges [158](#)
Sources and Targets privilege group
 description [158](#)
sql
 permissions by command [229](#)
 privileges by command [229](#)
SQL data service
 inherited permissions [196](#)
 permission types [196](#)
 permissions [196](#)
SSL certificate
 LDAP authentication [26](#)
 LDAP user authentication [22](#)
Sun Java System Directory Server
 LDAP authentication [22](#)
synchronization
 LDAP users [22](#)
 times for LDAP directory service [25](#)

synchronization (*continued*)
 users [106](#)
system memory
 increasing [120](#)
system-defined roles
 Administrator [177](#)
 assigning to users and groups [180](#)
 description [176](#)

T

targets
 privileges [158](#)
Test Data Manager
 administrator [115](#)
Tools privilege group
 domain [145](#)
 PowerCenter Repository Service [153](#)

U

UpdateColumnOptions
 substituting column values [199](#)
user accounts
 changing the password [109](#)
 created during installation [114](#)
 default [114](#)
 enabling [118](#)
 overview [114](#)
user activity logs
 convertUserActivityLog [121](#)
 getUserActivityLog [121](#)
 output formats [121](#)
user description
 invalid characters [117](#)
user security
 description [104](#)
users
 assigning to groups [118](#)
 invalid characters [117](#)
 large number of [120](#)
 managing [116](#)
 overview [108](#)
 privileges, assigning [180](#)
 roles, assigning [180](#)
 synchronization [106](#)
 system memory [120](#)
 valid name [117](#)

V

valid name
 groups [124](#)
 user account [117](#)
virtual schema
 inherited permissions [196](#)
 permissions [196](#)
virtual stored procedure
 inherited permissions [196](#)
 permissions [196](#)
virtual table
 inherited permissions [196](#)
 permissions [196](#)

W

web service

permission types [200](#)

permissions [200](#)

web service operation

permissions [200](#)

web service resource

permissions [200](#)

wfs

permissions by command [230](#)

wfs (*continued*)

privileges by command [230](#)

workflow

inherited permissions [194](#)

permissions [194](#)